Installable File Systems For OS/2 Version 3.0 OS/2 File Systems Department PSPC Boca Raton, Florida

February 13, 1998

This document includes a DRAFT description of the Installable File System Driver Interface for IBM OS/2 Standard Edition Version 3.0. *PLEASE DO NOT DISTRIBUTE THIS VERSION.*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS DOCUMENNT "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

IN NO EVENT WILL IBM BE LIABLE FOR ANY DAMAGES, INCLUDING BUT NOT LIMITED TO ANY LOST PROFITS, LOST SAVINGS OR ANY INCIDENTAL OR CONSEQUENTAL DAMAGES, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGES, OR FOR ANY CLAIM BY YOU BASED ON A THIRD PARTY CLAIM.

Some or all of the interfaces described in this document are unpublished. IBM reserves the right to change or delete them in future versions of OS/2, at IBM's sole discretion, without notice to you. IBM does not guarantee that compatability of your applications can or will be maintained with future versions of OS/2.

This document could include technical inaccuracies or typographical errors. It is possible that this document may contain reference to, or information about, IBM products, programming or services that are not announced in your country. Such references or information must not be construed to mean that IBM intends to announce such IBM products, programming or services in your country.

IBM may have patents or pending patent applications covering subject matter in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the IBM Director of Commercial Relations, IBM Corporation, Armonk NY 10504.

© Copyright International Business Machines Corporation 1991. All rights reserved.

Note to U.S. Government Users — Documentation related to restricted rights — Use, duplication or disclosure is subject to restrictions set forth in GSA ADP Schedule Contract with IBM Corp.

Contents

| Chapter 1. Installable File System Mechanism | 1-1 |
|---|------------|
| Installable File System Overview | |
| System Relationships | 1-1 |
| File I/O API | 1-2 |
| Buffer Management | 1-5 |
| Volume Management | 1-5 |
| | 1-5 |
| IPL Mechanism | 1-6 |
| OS/2 Partition Access | 1-6 |
| Permissions | |
| File Naming Conventions | 1-7 |
| Meta Character Processing | |
| FSD Pseudo-character Device Support | |
| Family API Issues | |
| FSD Utilities | |
| FSD Utility Support | 1-7 |
| FSD Utility Guidelines | |
| FSD Utility Interfaces | |
| Extended Attributes | |
| FEAs | 1-9 |
| GEAs | . 1-10 |
| FSD File Image | . 1-12 |
| FSD Attribute | |
| FSD Initialization | . 1-13 |
| OS/2 and DOS Extended Boot Structure and BIOS Parameter Block | |
| IFS Commands | . 1-16 |
| IFS = (CONFIG.SYS Command) | . 1-16 |
| File System Function Calls | |
| Application File I/O Notes | . 1-16 |
| Date/Time Stamps | . 1-17 |
| I/O Error Codes | . 1-17 |
| FSD System Interfaces | . 1-18 |
| Overview | . 1-18 |
| Data Structures | . 1-19 |
| Time Stamping | . 1-22 |
| FSD Calling Conventions and Requirements | . 1-22 |
| Error Codes | . 1-23 |
| Observer 0. EO Osmilas Develinas | 0 4 |
| Chapter 2. FS Service Routines | |
| FS_ALLOCATEPAGESPACE Adjust the size of paging file | |
| FS_ATTACH Attach to an FSD FS_CANCELLOCKREQUEST Cancel file record lock request | |
| • | |
| FS_CHDIR Change/Verify Directory Path | |
| FS_CHGFILEPTR Move a file's position pointer | |
| — | |
| FS_COMMIT Commit a file's buffers to Disk | |
| FS_COPY Copy a file | |
| FS_DELETE Delete a file FS_DOPAGEIO Perform paging I/O operations | |
| | |
| FS_EXIT End of process | 2-20 |

| FS_FILEATTRIBUTE Query/Set File Attribute | 2-21 |
|--|--------|
| FS_FILEINFO Query/Set a File's Information | 2-23 |
| FS_FILEIO Multi-function file I/O | 2-26 |
| FS_FILELOCKS Request a file record lock/unlock | 2-29 |
| FS_FINDCLOSE Directory Read (Search) Close | 2-32 |
| FS_FINDFIRST Find First Matching File Name(s) | |
| FS_FINDFROMNAME Find matching file name(s) starting from name | |
| FS_FINDNEXT Find next matching file name. | |
| FS_FINDNOTIFYCLOSE Close Find-Notify Handle | |
| FS_FINDNOTIFYFIRST Monitor a directory for changes. | |
| FS_FINDNOTIFYNEXT Resume reporting directory changes | |
| FS_FLUSHBUF Commit file buffers | |
| FS_FSCTL File System Control | |
| FS_FSINFO File System Information | |
| FS_INIT File system driver initialization | |
| - | |
| FS_IOCTL I/O Control for Devices | |
| FS_MKDIR Make Subdirectory | |
| FS_MOUNT Mount/unmount volumes | |
| FS_MOVE Move a file or subdirectory | |
| FS_NEWSIZE Change File's Logical Size | |
| FS_NMPIPE Do a remote named pipe operation. | |
| FS_OPENCREATE Open a file | |
| FS_OPENPAGEFILE Create paging file and handle | |
| FS_PATHINFO Query/Set a File's Information | . 2-70 |
| FS_PROCESSNAME Allow FSD to modify name after OS/2 | |
| canonicalization | 2-72 |
| FS_READ Read from a File | 2-73 |
| FS_RMDIR Remove Subdirectory | 2-75 |
| FS_SETSWAP Notification of swap-file ownership | 2-76 |
| FS_SHUTDOWN Shutdown file system | 2-77 |
| FS_VERIFYUNCNAME Verify UNC server ownership | 2-79 |
| FS_WRITE Write to a file | 2-80 |
| | |
| Chapter 3. FS Helper Functions | 3-1 |
| FSH_ADDSHARE Add a name to the share set | |
| FSH_CALLDRIVER Call Device Driver's Extended Strategy entry point | 3-5 |
| FSH_CANONICALIZE Convert a path name to a canonical form | |
| FSH_CHECKEANAME Check for valid EA name | |
| FSH_CRITERROR Signal hard error to daemon | |
| FSH_DEVIOCTL Send IOCTL request to device driver | |
| FSH DOVOLIO Transfer volume-based sector-oriented I/O | |
| FSH_DOVOLIO2 Send volume-based IOCTL request to device driver | |
| FSH_EXTENDTIMESLICE Notify kernel that temporarily increasing this | 017 |
| thread's time slice is advisable. | 3-19 |
| FSH_FINDCHAR Find first occurrence of character in string | |
| FSH_FINDDUPHVPB Locate equivalent hVPB | |
| FSH_FORCENOSWAP Force segments permanently into memory | |
| FSH_GETPRIORITY Get current thread's I/O priority | |
| FSH_GETVOLPARM Get VPB data from VPB handle | |
| — | |
| FSH_INTERR Signal an internal error | |
| FSH_IOBOOST Gives the current thread an I/O priority boost | |
| FSH_IOSEMCLEAR Clear an I/O event semaphore | |
| FSH_ISCURDIRPREFIX Test for a prefix of a current directory | |
| FSH_LOADCHAR Load a character from a string | . 3-30 |

| FSH_NAMEFROMSFN Get the full path name from an SFN. | 3-31 |
|---|------|
| FSH_PREVCHAR Decrement a character pointer | 3-32 |
| FSH_PROBEBUF Check user address validity | 3-33 |
| | 3-35 |
| | 3-37 |
| FSH_QUERYSERVERTHREAD Query if the current thread is a server | |
| | 3-38 |
| _ 0 | |
| | 3-40 |
| | 3-41 |
| | 3-43 |
| | |
| FSH_SEMCLEAR Clear a semaphore | |
| | |
| — I | 3-48 |
| | 3-49 |
| — | 3-50 |
| — | 3-51 |
| — | |
| | |
| FSH_UPPERCASE Uppercase asciiz string | 3-54 |
| FSH_WILDMATCH Match using OS/2 wildcards | |
| FSH_YIELD Yield processor to higher-priority thread | 3-56 |
| | |
| Chapter 4. Remote IPL / Bootable IFS | |
| Operational Description | |
| FAT Boot Procedure | |
| BIFS Boot Procedure | |
| Interfaces | |
| BlackBox/OS2LDR interface | |
| miniFSD/OS2KRNL interface | |
| Stage 1 Interfaces | |
| Stage 2 Interfaces | |
| Stage 3 Interfaces | |
| Imbedded Device Driver Helpers | |
| Special Considerations | 4-9 |
| | 4-10 |
| | 4-11 |
| | 4-12 |
| | 4-13 |
| | 4-15 |
| = | 4-16 |
| | 4-17 |
| I | 4-18 |
| | 4-19 |
| | 4-20 |
| — | 4-21 |
| | 4-22 |
| | 4-23 |
| | 4-24 |
| | 4-25 |
| | 4-26 |
| MFSH_SETBOOTDRIVE Change boot drive number kept by the OS/2 | |
| kernel | 4-27 |

| Chapter 5. Index | . 5-1 |
|---|-------|
| MFSH_VIRT2PHYS Convert virtual to physical address | 4-30 |
| MFSH_UNPHYSTOVIRT Mark completion of use of virtual address | 4-29 |
| MFSH_UNLOCK Unlock a segment | 4-28 |

Chapter 1. Installable File System Mechanism

The OS/2 Installable File System (IFS) Mechanism supports the following: Coexistence of multiple, active file systems in a single PC Multiple logical volumes (partititions) Multiple and different storage devices Redirection or connection to remote file systems File system flexibility in managing its data and I/O for optimal performance Transparency at both the user and application level Standard set of File I/O API Existing logical file and directory structure Existing naming conventions File system doing its own buffer management File system doing file I/O without intermediate buffering Extensions to the Standard File I/O API (FSCTL) Extensions to the existing naming conventions IOCTL type of communication between a file system and a device driver

Installable File System Overview

System Relationships

The Installable File System (IFS) Mechanism defines the relationships among the operating system, the file systems, and the device drivers. The basic model of the system is represented in Figure 1-1 on page 1-2.




Figure 1-1. System relationships for Installable File Systems

The file system request router directs file system function calls to the appropriate file system for processing.

The file systems manage file I/O and control the format of information on the storage media. An installable file system (FS) will be referred to as a file system driver (FSD).

The FS Helper Routines provide a variety of services to the file systems.

The device drivers manage physical I/O with devices. Device drivers do not understand the format of information on the media.

File I/O API

Standard file I/O is performed through the Standard File I/O API. The application makes a function call and the file system request router passes the request to the correct file system for processing. See Figure 1-2 on page 1-3.




Figure 1-2. Standard File I/O

New API may be provided by a file system to implement functions specific to the file system or not supplied through the standard file I/O interface. New API are provided in a dynamic link library that uses the DosFsCtl standard function call to communicate with the specific file system (FSD). See Figure 1-3.




Figure 1-3. Extended File I/O

Buffer Management

In 2.0 the FAT buffer management helpers were removed because of lack of use by any 1.x FSD. FSDs should handle all buffer/cache management themselves.

The FSD moves all data requiring partial sector I/O between the application's buffers and its cache buffers. The FS helper routines initiate the I/O for local file systems.

Volume Management

Volume management (that is, detecting when the wrong volume is mounted and notifying the operator to take corrective action) is handled directly through OS/2 and the device driver. Each FSD is responsible for generating a volume label and 32-bit volume serial number. These are stored in a reserved location in logical sector zero at format time. Because an FSD is the only system component to touch this information, an FSD is not required to store it in a particular format. OS/2 calls the FSD to perform operations that might involve it. The FSD is required to update the volume parameter block (VPB) whenever the volume label or serial number is changed.

When the FSD passes an I/O request to an FS helper routine, the FSD passes the 32-bit volume serial number and the user's volume label (through the VPB). When the I/O is performed, OS/2 compares the requested volume serial number with the current volume serial number it maintains for the device. This is an in-storage test (no I/O required) performed by checking the drive parameter block's (DPB) VPB of the volume mounted on the drive. If unequal, OS/2 signals the critical error handler to prompt the user to insert the volume having the serial number and label specified.

When OS/2 detects a media change in a drive, or the first time a volume is accessed, OS/2 determines which FSD is responsible for managing I/O to that volume. OS/2 allocates a VPB and polls the installed FSDs (by calling the FS_MOUNT entry point) until an FSD indicates that it does recognize the media. If the volume serial number and label returned by the FS_MOUNT call matchs the serial number and label in an existing VPB, OS/2 will call FS_MOUNT to unmount the new access and will continue to access the media through the previous VPB.

Note: The FAT FSD is the last in the list of installed FSDs and acts as the default FSD when no other FSD recognition takes place.

Connectivity

There are two classes of file system drivers:

- FSDs that use a block device driver to do I/O to a local or remote device. These are called *local file systems*.
- FSDs that access a remote system without a block device driver. These are called *remote file systems*

The connection between a drive letter and a remote file system is achieved through a command interface provided with the FSD (FS_Attach).

When a local volume is first accessed, OS/2 sequentially asks each installed FSD to accept the media, by calling each FSD's FS_MOUNT entry point. If no FSD accepts the media, it is then assigned to the default FAT file system. Any further

attempt that is made to access an unrecognized media, other than by FORMAT, results in an 'Invalid media format' message.

When a volume has been recognized, the relationship between drive, FSD, volume serial number, and volume label is remembered. The volume serial number and label are stored in the volume parameter block (VPB). The VPB is maintained by OS/2 for open files (I/O based on file-handles), searches, and buffer references. The VPB represents the media.

Subsequent requests for a volume that has been removed require polling the installed FSDs for volume recognition by calling FS_MOUNT. The volume serial number and volume label of the VPB returned by the recognizing FSD and the existing VPB are compared. If the test fails, OS/2 signals the critical error handler to prompt the user for the correct volume.

The connection between media and VPB is remembered until all open files on the volume are closed and search and cache buffer references are removed. Only volume changes cause a redetermination of the media at the time of next access.

IPL Mechanism

If Boot Manager is not installed, a primary DOS disk partition (type 1, 4, or 6) may be used to boot the system. If Boot Manager is installed, a logical partition may contain the code to boot OS/2, but the boot code can not be located beyond cylinder 1024 since BIOS is used to read the disk prior to loading the device driver(s). The code for FSDs may reside in any partition readable by a previously installed FSD. An IFS partition must be a type 7 partition.

The OS/2 boot volume will have a Bootrecord at logical sector 0 which will invoke the basic file system code to start the loading process. The root directory of this volume will contain a mini-file system in OS2BOOT, a kernel loader in OS2LDR, the OS/2 kernel in OS2KRNL, and the CONFIG.SYS file.

Device drivers and FSDs are loaded in the order they appear in CONFIG.SYS and are considered elements of the same ordered set. Therefore, both device drivers and FSDs may be loaded from installed file systems as long as they are started in the proper order. For example:

DEVICE = c:\diskdriv.sys REM Block device D: is now defined. (diskdriv.sys controls this.) IFS = c:\fsd\newfsl.fsd REM If we assume that D: contains a fixed newfsl type partition, REM then we're now ready to use D: to load the device driver and REM FSD for E:. DEVICE = d:\root\dev\special.dev REM Block device e: is now defined. IFS = d:\root\fsd\special.fsd REM E: can now be read. DEVICE = e:\music

OS/2 Partition Access

Access to the OS/2 partition on a bootable, logically partitioned media is through the full OS/2 function set. See *OS/2 Version 3.0 Physical Device Driver Reference* for a detailed description of the disk partitioning design.

Permissions

There are no secure file system clients identified for OS/2 Version 3.0 incorporating the IFS architecture.

File Naming Conventions

See *OS/2 Version 3.0 Programming Guide* for a detailed description of OS/2 Version 3.0 file naming conventions.

It is currently a requirement that an FSD supports case insensitive searching if they are to be completely compatible with OS/2. The large number of DOS, Windows and OS/2 applications that depend on case insensitive searching make it unlikely that this requirement will be removed. At this time, problems caused by an FSD only supporting case sensitive searching are the responsibily of the owners of the FSD.

Meta Character Processing

See *OS/2 Version 3.0 Programming Guide* for a detailed description of OS/2 Version 3.0 meta character processing.

FSD Pseudo-character Device Support

A pseudo-character device (single file device) may be redirected to an FSD. The behavior of this file is very similar to the behavior of a normal OS/2 character device. It may be read from (DosRead) and written to (DosWrite). The difference is that the DosChgFilePtr and DosFileLocks functions can also be applied to the file. The user would perceive this file as a device name for a non-existing device. This file is seen as a character device because the current drive and directory have no effect on the name. That is what happens in OS/2 today for character devices.

The format of an OS/2 pseudo-character device name is that of an ASCIIZ string in the format of an OS/2 file name in a subdirectory called \DEV\. The pseudo device name XXX is accessible at the API level (DosQFsAttach) through the path name '\DEV\XXX'.

Family API Issues

Since the IFS Mechanism is not present in any release of DOS, FAPI will not be extended to support the new interfaces.

FSD Utilities

FSD Utility Support

Each FSD is required to provide a single .DLL executable module that supports the OS/2 FORMAT, CHKDSK, SYS, and RECOVER utilities. The FS-supported executable will be invoked by these utilities when performing a FORMAT, CHKDSK, SYS, or RECOVER function for that file system. The command line that was passed to the utility will be passed unchanged to the FS-specific executable.

The procedures that support these utilities reside in a file called U<fsdname>.DLL, where <fsdname> is the name returned by DosQFsAttach. Since in OS/2 Version 3 DLL names are limited to 8.3, <fsdname> should be a maximum of 7 bytes long.

FSD Utility Guidelines

The FSD utility procedures are expected to follow these guidelines:

No preparation is done by the base utilities before they invoke the FSD utility procedure. Therefore, base utilities do not lock drives, parse names, open drives, etc. This allows maximum flexibility for the FSD.

The FSD utility procedure is expected to protect the partition from access if they are doing direct access updates. The category 8 DosIOCTLs DSK_LOCKDRIVE and DSK_UNLOCKDRIVE should be used to protect the drive from access. The DSK_REDETERMINEMEDIA call must be made after FORMAT if the volume label and/or serial number has been modified- it will allow the VPB and DPB to be updated appropriately.

The FSD utility procedures are expected to follow the standard conventions for the operations that they are performing, for example, /F for CHKDSK implies "fix" and the /L for FORMAT implies a *long* or certified format. All functional levels are not required, but if an equivalent function is supplied, the same parameter should be used.

The FSD procedures may use stdin, stdout, and stderr, but should be aware that they may have been redirected to a file or device.

- It is the responsibility of the FSD procedures to worry about volumes being changed while the operation is in progress. The normal action would be to stop the operation when such a situation is detected.
- When the FSD procedures are called, they will be passed argc, argv, and envp, that they can use to determine the operations.

FSD procedures are responsible for displaying relevant prompts and messages.

FSD utility procedures must follow the standard convention of entering the target drive as specified for each utility.

FSD Utility Interfaces

All FSD utility procedures are called with the same arguments:

int far pascal Ufsdname.CHKDSK(int argc, char far \far \argv, char far \far \nvp);

int far pascal Ufsdname. FORMAT
(int argc, char far \far argv, char far \far argv);

int far pascal Ufsdname.RECOVER(int argc, char far \far \argv, char far \far \text{argv});

int far pascal Ufsdname.SYS(int argc, char far \far \argv, char far \far \argv, char far \far \envp);

where argc, argv, and envp have the same semantics as the corresponding variables in C.

Extended Attributes

Extended attributes (EAs) are a mechanism whereby an application can attach information to a file system object (directories or files) describing the object to another application, to the operating system, or to the FSD managing that object.

EAs associated with a file object are not part of a file object's data, but are maintained separately and managed by the file system that manages that object.

Each extended attribute consists of a name and a value. An EA name consists of ASCII text, chosen by the application developer, that is used to identify a particular EA. EA names are restricted to the same character set as a filename. An EA value consists of arbitrary data, that is, data of any form. Because of this OS/2 does not check data that is associated with an EA.

So that EA data is understandable to other applications, conventions have been established for:

Naming EAs Indicating the type of data contained in EAs

In addition, a set of standard EAs (SEAs) have been defined. SEAs define a common set of information that can be associated with most files (for example, file type and file purpose). Through SEAs, many applications can access the same, useful information associated with files.

Applications are not limited to using SEAs to associate information with files. They may define their own application-specific extended attributes. Applications define and associate extended attributes with a file object through file system function calls.

See the *OS/2 Version 3.0 Programming Guide* for a complete description of EA naming conventions and data types and standard extended attributes. See also the *OS/2 Version 3.0 Control Program Programming Reference* for a complete description of the file system function calls.

EAs may be viewed as a property list attached to file objects. The services for manipulating EAs are: add/replace a series of name/value pairs, return name/value pairs given a list of names, and return the total set of EAs.

There are two formats for EAs as passed to OS/2 Version 3.0 API: Full EAs (FEA) and Get EAs (GEA).

FEAs

FEAs are complete name/value pairs. In order to simplify and speed up scanning and processing of these names, they are represented as length-preceded data. FEAs are defined as follows:

struct FEA {

```
unsigned char fEA; //byte of flags X
unsigned char cbName; //length of name X
unsigned short cbValue; //length of value X
unsigned char szName[]; //asciiz name X
unsigned char aValue[]; //free format value X
```

};

There is only one flag defined in fEA at this time. That is 0x80 which is fNeedEA. Setting the flag marks this EA as needed for the proper operation on the file to which it is associated. Setting this bit has implications for access to this file by old applications, so it should not be set arbitrarily.

If a file has one or more NEED EAs, old applications are not allowed to open the file. For DOS mode applications to access files with NEED EAs, they must have

the EA bit set in their exe header. For OS/2 mode, only applications with the NEWFILES bit set in the exe header may open files with NEED EAs. The OS/2 IFS mechanism supports this restriction using the information in the pfgenflag returned by the FS_OPENCREATE routine.

The name length does not include the trailing NUL. The maximum EA name length is 255 bytes. The minimum EA name length is 1 byte. The characters that form the name are legal filename characters. Wildcard characters are not allowed. EA names are case-insensitive and should be uppercased. The FSD should call FSH_CHECKEANAME and FSH_UPPERCASE for each EA name it receives to check for invalid characters and correct length, and to uppercase it.

The FSD may not modify the flags.

A list of FEAs is a packed set of FEA structures preceded by a length of the list (including the length itself) as indicated in the following structure:

FEA lists are used for adding, deleting, or changing EAs. A particular FSD may store the EAs in whatever format it desires. Certain EAs may be stored to optimize retrieval.

Name lengths of 0 are illegal and are considered in error. A value length of 0 has special meaning. Setting an EA with a value length of 0 will cause that attribute to be deleted (if possible). Upon retrieval, a value length of 0 indicates that the attribute is not present.

Setting attributes contained in an FEA list does not treat the entire FEA list as atomic. If an error occurs before the entire list of EAs has been set, all, some, or none of them may actually remain set on the file. No program should depend on an EA set being atomic to force EAs to be consistent with each other. Programs must be careful not to depend on atomicity, since a given file system is not required to provide it.

GEAs

A GEA is an attribute name. Its format is:

```
struct GEA {
    unsigned char cbName; /length of name X
    unsigned char szName[]; /length of name X
};
```

The name length does not include the trailing NUL.

Name lengths of 0 are illegal and are considered in error.

A list of GEAs is a packed set of GEA structures preceded by a length of the list (including the length itself) as indicated in the following structure:

```
struct GEAList {
    unsigned long cbList;
    struct GEA list[];
    /packed set of GEAs X
};
```

GEA lists are used for retrieving the values for a particular set of attributes. A GEA list is used as input only.

Manipulation of extended attributes is associated with access permission to the associated file or directory. For querying and setting file EAs, read and write/read permission, respectively, for the associated file is required. No directory create or delete will occur while querying EAs for that directory.

For handle-based operations on extended attributes, access permission is controlled by the sharing/access mode of the associated file. If the file is open for read, querying the extended attributes is allowed. If the file is open for write, setting the extended attributes is allowed. These operations are supported by the FSD in FS_FILEINFO. OS/2 will provide the sharing/access checks for the FSD.

For path-based manipulation of extended attributes, the associated file or directory will be added to the sharing set for the duration of the call. The requested access permission for setting EAs is write/deny-all and for querying EAs is read/deny-write. The path-based API are DosQPathInfo, DosSetPathInfo, and DosFindFirst2/Next. These API map to FS_PATHINFO, FS_FINDFIRST, FS_FINDNEXT and FS_FINDFROMNAME.

For create-only operations of extended attributes, the extended attributes are set without examining the sharing/access mode of the associated file/directory. These operations are performed by APIs DosOpen2 and DosMkDir2 which result in calls to FS_OPENCREATE and FS_MKDIR respectively.

The routing of EA requests is accomplished by the IFS routing mechanism. EA requests that apply to names are routed to the FSD attached to the specified drive. Those requests that apply to a handle (file or directory) are routed to the FSD attached to the handle. No interpretation of either FEA lists nor GEA lists is performed by the IFS router.

Note: It is the responsibility of each FSD to provide support for EAs.

It is expected that some FSDs will be unable to store EAs; for example, UNIX- and MVS-compatible file systems. However, the growing use of EAs in applicationsespecially the object-oriented applications means there will be reduced functionality if an FSD does not support EAs.

Note: The FAT FSD implementation will provide for the complete implementation of EAs. There will be no special EAs for the FAT FSD.

All EA manipulation is performed using the following structure: The relevance of each field is described within each API.

```
struct EAOP {
```

struct GEAList far \fpGEAList; \land GEA setXstruct FEAList far \fpFEAList; \land FEA setXunsigned long offError; \land offset of FEA err X

};

See the descriptions of the file system function calls in *OS/2 Version 3.0 Control Program Programming Reference* for the relevance of each field.

In OS/2 Version 3.0, values of cbList greater than (64K-1) are not allowed. This limitation is caused by the requirement of supporting the FS_FILEINFO and FS_PATHINFO level 4 call to return all EAs. Until this interface changes or file systems are converted to 32 bit, this limitation is expected to continue. It is the

responsibility of the FSD to not permit extended attributes to be added so that the entire extended attribute set exceeds 64K. This will prevent the level 4 FS_FILEINFO and FS_PATHINFO query from overflowing..

FSD File Image

An FSD loads from a file which is in the format of a standard OS/2 dynamic link library file. Exactly one FSD resides in each file. The FSD exports information to OS/2 using a set of predefined public names.

The FSD is initialized by a call to the exported entry point FS_INIT.

FS entry points for Mount, Read, Write, etc. are exported with known names as standard far entry points.

The FSD exports its name as a public ASCIIZ character string under the name 'FS_NAME'. All comparisons with user-specified strings are done similar to file names; case is ignored and embedded blanks are significant. FS_NAMEs, however, may be input to applications by users. Embedded blanks should be avoided. The name exported as FS_NAME need NOT be the same as the 1-8 FSD name in the boot sector of formatted media, although it may be. The ONLY name the kernel pays any attention to, and the only name accessible to user programs through the API, is the name exported as FS_NAME.

In addition to various entry points, the FSD must export a dword bit vector of attributes. Attributes are exported under the name 'FS_ATTRIBUTE'. FS_ATTRIBUTE specifies special properties of the FSD and is described in the next section.

FSD Attribute

The format of the OS/2 FS_ATTRIBUTE is defined in Figure 1-4 and the definition list that follows it.

Figure 1-4. OS/2 FSD Attribute

Bits Description

31 FSD Additional attributes. If 1, FSD has additional attributes.

If 1, FSD has additional attributes. If 0, FS_ATTRIBUTE is the only FSD attribute information.

- 30-28 VERSION NUMBER FSD version number.
- 27-5 RESERVED
- 4 FSA_PSVR Remote Pipe bit.

Set if FSD manages remote pipes.

3 FSA_LVL7 - QPathInfo Level 7 bit.

Set if FSD is case-preserving. If this bit is set, the kernel will call the FS_PATHINFO entry point with a level equal to 7. The output buffer is to be filled with a case-preserved copy of the path that was passed in by the user.

2 FSA_LOCK - File I/O bit.

Set if FSD wants to see file locking/unlocking operations and compacted file I/O operations. If not set, the file I/O calls will be broken up into individual lock/unlock/read/write/seek calls and the FSD will not see the lock/unlock calls. FSDs that do not support file locking can set this bit to enable compacted file I/O operations. FSDs that do support file locking will be responsible for all lock checking; OS/2 will not perform any checking for locks if this bit is set. The FSD will be responsible for handling the contention between multiple processes due to file locking- in other words, the FSD is responsible for preventing deadlocks. Since DOS applications use FS_FILEIO and OS/2 applications use FS_FILELOCKS, the FSD will need to support both entry points if it needs to support file locking under both DOS and OS/2.

1 FSA_UNC - Universal Naming Convention bit. Set if FSD supports

Set if FSD supports the Universal Naming Convention. OS/2 Version 3.0 supports multiple loaded UNC redirectors.

0 FSA_REMOTE - Remote File System(Redirector).

This bit tells the system whether the FSD uses static or dynamic media attachment. Local FSDs always use dynamic media attachment. Remote FSDs always use static media attachment. This bit is clear if it is a dynamic media attachment and set, if a static attachment. No FSD supports both static and dynamic media attachment. To support proper file locking, a remote FSD should also set the FSA_LOCK bit.

FSD Initialization

FSD initialization occurs at system initialization time. FSDs are loaded through the IFS= configuration command in CONFIG.SYS. Once the FSD has been loaded, the FSD's initialization entry point is called to initialize it.

FSDs are structured the same as dynamic link library modules. Once an FSD is loaded, the initialization routine FS_INIT is called. This gives the FSD the ability to process any parameters that may appear on the CONFIG.SYS command line, which are passed as a parameter to the FS_INIT routine. A LIBINIT routine in an FSD will be ignored.

OS/2 FSDs initialize in protect mode. Because of the special state of the system, an FSD may make dynamic link system calls at init-time.

The list of systems calls that an FSD may make are as follows:

DosBeep DosChgFilePtr DosClose DosDelete **DosDevConfig** DosDevloCtl DosFindClose DosFindFirst DosFindNext DosGetEnv DosGetInfoSeg DosGetMessage DosOpen DosPutMessage DosQCurDir DosQCurDisk DosQFileInfo DosQFileMode DosQSysInfo DosRead DosWrite

The FSD may not call ANY FS helper routines at initialization time.

Note that multiple code and data segments are not discarded by the loader as in the case of device drivers.

The FSD may call DosGetInfoSeg to obtain access to the global and process local information segments. The local segment may be used in the context of all processes without further effort to make it accessible and has the same selector. The local infoseg is not valid in real mode or at interrupt time.

OS/2 and DOS Extended Boot Structure and BIOS Parameter Block

The Extended Boot structure is as follows:

| Boot_jmp[3]; |
|---|
| Boot_OEM[8]; |
| ot_BPB; |
| Boot_DriveNumber; |
| Boot_CurrentHead; |
| Boot_Sig = 41; \land Indicate Extended Boot \land |
| Boot_Serial[4]; |
| Boot_Vol_Label[11]; |
| Boot_System_ID[8]; |
| |
| |

Where

Serial is the 32-bit binary volume serial number for the media.

System_ID is an 8-byte name written when the media is formatted. It is used by FSDs to identify their media but need not be the same as the name the FSD exports via FS_NAME and is NOT the name users employ to refer to the FSD. (They may, however, be the same names). However, this name does need to match the FSD name used to create the U<fsdname>.DLL that contains the utilities.

Vol_Label is the 11-byte ASCII label of the disk/diskette volume. FAT file systems must ALWAYS use the volume label in the root directory for compatibility reasons. If at all possible, an FSD should use the volume label field in the boot sector.

The extended BPB structure is a super-set of the conventional BPB structure, as follows:

struct Extended_BPB {

| unsigned short | BytePerSector; |
|----------------|-------------------|
| unsigned char | SectorPerCluster; |
| unsigned short | ReservedSectors; |
| unsigned char | NumberOfFats; |
| unsigned short | RootEntries; |
| unsigned short | TotalSectors; |
| unsigned char | MediaDescriptor; |
| unsigned short | SectorsPerFat; |
| unsigned short | SectorsPerTrack; |
| unsigned short | Heads; |
| unsigned long | HiddenSectors; |
| unsigned long | Ext_TotalSectors; |
| }; | |

IFS Commands

IFS = (CONFIG.SYS Command)

An FSD is loaded and initialized at system start-up when an IFS= statement is encountered in CONFIG.SYS. The syntax of this command is as follows:

IFS=drive:path\name.ext parms

where

| drive:path\name.ext | specifies the FSD to load and initialize. |
|---------------------|--|
| parms | represents an FSD-defined string of initialization parameters. |

See the OS/2 Version 3.0 Online Command Reference for a detailed description of this command.

File System Function Calls

The OS/2 Version 3.0 Control Program Programming Reference gives a detailed description of the 32-bit file system calls new for OS/2 Version 3.0 See the OS/2 Version 3.0 Programming Guide for a description of how to use these calls. For detailed descriptions of the 16-bit file system calls see the OS/2 Version 1.3 Control Program Programming Reference, and the OS/2 Version 1.3 Programming Guide on how to use these calls.

Note: The data structures for some of the file system calls have changed in their 32-bit implementations. The kernel will handle all remapping between the 32-bit structures and the 16-bit structures used by individual FSDs.

Application File I/O Notes

File handle values of 0xFFFF do not represent actual file handles but are used throughout the file system interface to indicate specific actions to be taken by the file system. Usage of this special file handle where it is not expected by the file system will result in an error.

A 16 bit pointer is defined to be 000x:0000, where the least significant two bits in x is the ring number. Consequently, a ring 3 NULL pointer can be passed in as 0003:0000.

File systems that conform to the Standard Application Program Interface (Standard API) may not necessarily support all the described information kept on a file basis. When this is the case, FSDs are required to return to the application a null (zero) value for the unsupported parameter.

An FSD may support version levels of files.

Date/Time Stamps

The format of OS/2 dates are show below in Figure 1-5.




Figure 1-5. OS/2 Date Format

| Bits | Description |
|------|---|
| 15-9 | YEARS - Number of years since 1980. |
| 8-5 | MONTH - is the month of the year (1-12) |
| 4-0 | DAY - is the day of the month (1-31) |

The format of OS/2 times are show below in Figure 1-6.

Figure 1-6. OS/2 Time Format

Bits Description

- 15-9 HOUR is the hour of the day (0-23)
- 8-5 MINUTE is the minute of the hour (0-59)
- 4-0 2-SECOND is the second of the minute(in increments of 2) (0-29)

I/O Error Codes

Some file system functions may return device-driver/device-manager generated errors. These include:

ERROR_WRITE_PROTECT - the media in the drive has write-protection enabled.

ERROR_BAD_UNIT - there is a breakdown of internal consistency between OS/2's mapping between logical drive and device driver. Internal Error.

ERROR_NOT_READY - the device driver detected that the device is not ready.

ERROR_BAD_COMMAND - there is a breakdown of internal consistency between OS/2's idea of the capability of a device driver and that of the device driver.

ERROR_CRC - the device driver has detected a CRC or ECC error. The data in the sector read has become corrupted and can not be corrected by the error correction code.

ERROR_BAD_LENGTH - there is a breakdown of internal consistency between OS/2's idea of the length of a request packet and the device driver's idea of that length. Internal Error.

ERROR_SEEK - the device driver detected an error during a seek operation.

ERROR_NOT_DOS_DISK - the disk is not recognized as being OS/2 manageable.

ERROR_SECTOR_NOT_FOUND - the device is unable to find the specific sector.

ERROR_OUT_OF_PAPER - the device driver has detected that the printer is out of paper.

ERROR_WRITE_FAULT - other write-specific error.

ERROR_READ_FAULT - other read-specific error.

ERROR_GEN_FAILURE - other error.

There are also errors defined by and specific to the device drivers. These are indicated by either 0xFF or 0xFE in the high byte of the error code.

Note: Error codes listed in the function call descriptions in the *OS/2 Version 3.0 Control Program Programming Reference* are not complete. They are errors most likely to be returned by the FS router and the FAT file system. Each FSD may generate errors based upon its own circumstances. However, applications may be coded to expect the return codes to be limited to the ones in the documentation and may consequently fail, so it is wise to attempt to conform when possible. In addition, the error codes returned to FS_IOCTL are restricted and may be modified before being returned to the user. For FSD specific requirements FS_FSCTL is recommended.

FSD System Interfaces

Overview

Installable file system entry points are called by the kernel as a result of action taken through the published standard file I/O application programming interface in OS/2 Version 3.0.

Installable file systems are installed as OS/2 dynamic link library modules. Unlike device drivers, they may include any number of segments, all of which will remain after initialization, unless the FSD itself takes some action to free them.

An FSD exports FS entries to the OS/2 kernel using standard PUBLIC declaractions. Each FS entry is called directly. The OS/2 kernel manages the association between internal data structures and FSDs.

When a file system service is required, OS/2 assembles an argument list, and calls the appropriate FS entry for the relevant FSD. If a back-level FSD is loaded, the OS/2 kernel assures that all arguments passed and all structures passed are understood by the FSD.

Application program interfaces that are unsupported by an FSD receive an UNSUP-PORTED FUNCTION error from the FSD.

Certain routines, for example, FS_PROCESSNAME, may provide no processing, no processing is needed, or processing does not make sense. These routines return no error, not ERROR_NOT_SUPPORTED.

Data Structures

OS/2 data structures that include a pointer to the file system driver, as well as file system specific data areas are:

the CDS (current directory structure) the SFT (system file table entry), the VPB (volume parameter block) the file search structures.

File system service routines are generally passed pointers to two parameter areas, in addition to read-only parameters which are specific to each call. The FSD does not need to verify these pointers. The two parameter areas contain file-system-independent data which is maintained jointly by OS/2 and the file system driver and file-system-dependent data which is unused by OS/2 and which may be used by the file system driver. The file system driver is generally permitted to use the file-system- dependent information in any way: The file-system-dependent information may contain all the information needed to describe the current state of the file or directory, or it may contain a handle which will direct it to other information about the file maintained within the FSD. Handles must be GDT selectors because any SFT, CDS, or VPB may be seen by more than one process. File-system-dependent and file-system-independent parameter areas are defined by data structures described in the remainder of this section.

Disk media and file system layout

are described by the following structures. The data which is provided to the file system may depend on the level of file system support provided by the device driver attached to the block device. These structures are relevant only for local file systems.

| truct vpfsi { | | | |
|----------------------|---------------|-------------------------------|---------|
| unsigned long | vpi_vid; | ∧32-bit volume ID | Х |
| unsigned long | vpi_hDEV; | Andle to the device d | river X |
| unsigned shor | t vpi_bsize; | ∧sector size in bytes | Х |
| unsigned long | vpi_totsec; | ∧total number of sectors | Х |
| unsigned shor | t vpi_trksec; | ∧sectors per track | Х |
| unsigned shor | t vpi_nhead; | ∧number of heads | Х |
| char | vpi_text[12 |]; \ASCIIZ volume name | Х |
| void far \setminus | | ∧device capability structu | ire X |
| void far \setminus | vpi_pVCS; | Avolume characteristics | Х |
| unsigned char | vpi drive; | \wedge drive (0=A) | Х |
| unsigned char | vpi unit; | ∕unit code | Х |
| unsigned short | 1 = / | ∧flags for memory restriction | ons X |

/\VPI_FLAGS Definitions: X

#define VPB_ABOVE16M_ALLOWED 0x0001 /The DD for this volume can access X /above 16 M. X

 \land Predefined volume IDs: \land

| ∧Unique ID for vpb_ #define UNREAD_II | ID field for unreadable media D 0x534E4A52L | a. X ∧Stored as (bytes) 0x52,4A,4 | 4E,53. | Х |
|---|--|--------------------------------------|--------|---|
| ∧Unique ID for vpb_ ∧cannot be normally | ID field for damaged volume mounted). | (recognized by IFS but | Х | Х |
| #define DAMAGED_ | _ID θxθL | \land Stored as (bytes) 0,0,0,0. X | | |
| \land file system dependent - volume parameters $𝔅$ | | | | |
| <pre>struct vpfsd { char };</pre> | vpi_work[36]; /\work area | Х | | |

Per-disk current directories

are described by the following structures. These structures can only be modified by the FSD during FS_ATTACH and FS_CHDIR operations.

 $\wedge file \; system \; independent$ - current directories ${\tt X}$

| struct cdfsi { | | | |
|--|---|---|---|
| unsigned short cdi_hVPB; | ∧VPB handle for associated device X | | |
| unsigned short cdi_end; | \wedge offset to root of path X | | |
| char cdi_flags; | ∧FS independent flags | Х | |
| char cdi_curdir[260]; | \wedge text of current directory X | | |
| }; | | | |
| ∧bit values for cdi_flags (state of cdfsd a #define CDI_ISVALID 0x80 #define CDI ISROOT 0x40 | structure X ∧format is known ∧cur dir == root | | X |
| #define CDI_ISCURRENT 0x20 | | | ~ |
| ∕\file system dependent - current directories X | | | |
| <pre>struct cdfsd { char cdd_work[8]; };</pre> | ∧work area | | Х |

Open files

are described by data initialized at file open time and discarded at the time of last close of all file handles which had been associated with that open instance of that file. There may be multiple open file references to the same file at any one time.

All time stamps on files are stamped and propagated to other SFTs by OS/2 when the file is closed or committed (flushed). For example, if a file is opened at time 1, written at time 2, and closed at time 3, the last write time is time 3.

Subdirectories need only have creation time stamps because the last write and last read time stamps on subdirectories are either very difficult to implement (propagate up to parent subdirectories), or are not very useful. An FSD, however, may implement them. FSDs are required to support direct access opens. These are indicated by a bit set in the sffsi.sfi_mode field.

 \wedge file system independent - file instance X

| struct sffsi { | | | |
|--|---|----|---|
| unsigned long sfi_mode; | ∧access/sharing mode | Х | |
| unsigned short sfi_hVPB; | ∕\volume info | | Х |
| unsigned short sfi_ctime; | ∧file creation time | Х | |
| unsigned short sfi_cdate; | ∧file creation date | Х | |
| unsigned short sfi_atime; | ∧file access time | Х | |
| unsigned short sfi_adate; | ∧file access date | Х | |
| unsigned short sfi_mtime; | ∧file modification time | Х | |
| unsigned short sfi_mdate; | ∧file modification date | Х | |
| unsigned long sfi_size; | ∕size of file | Х | |
| unsigned long sfi_position; | ∧read/write pointer X | | |
| ∕the following may be of use in | sharing checks X | | |
| unsigned short sfi_UID; | ∧user ID of initial opener | Х | |
| unsigned short sfi_PID; | Aprocess ID of initial opener | χ | |
| unsigned short sfi_PDB; | $\triangle PDB$ (in 3x box of initial opener) | χ | |
| | \system file number of file instance X | | |
| unsigned char sfi_tstamp; | ∧time stamps flag | Х | |
| unsigned short sfi_type; | ∧type of object opened | Х | |
| unsigned long sfi_pPVDBFil; | | ·χ | |
| unsigned char sfi_DOSattr; | \DOS file attributes D/S/A/H/R | Х | |
| }; ∧sfi_tstamps flags X | , <u>200</u> | ~ | |
| #define ST_SCREAT 1 | ∧stamp creation time | | Х |
| #define ST_PCREAT 2 | ∧propagate creation time | | Х |
| #define ST_SWRITE 4 | ∧stamp last write time | | Х |
| #define ST_PWRITE 8 | ∧propagate last write time | | Х |
| #define ST_SREAD 16 | ∧stamp last read time | | Х |
| #define ST_PREAD 32 | ∧propagate last read time | | Х |
| ∕sfi_type flags X | | | |
| #define STYPE_FILE 0 | ∧file | | Х |
| #define STYPE_DEVICE 1 | ∧device | | Х |
| #define STYPE_NMPIPE 2 | ∧named pipe | | Х |
| #define STYPE_FCB 4 | ∧fcb sft | | Х |
| Afile system dependent - file instance | ۶X | | |
| struct sffsd { | | | |
| char sfd_work[30]; | ; /work area | | Х |
| }; | | | |
| | | | |
| | | | |

The Program Data Block, or PDB (sfi_pdb), is the unit of sharing for DOS mode processes. For OS/2 mode processes, the unit of sharing is the Process ID, PID (sfi_pid).

FSDs should use the combination PDB, PID, UID as indicating a distinct process.

File search records

 $\wedge file \ system \ independent$ - file search parameters ${\tt X}$ struct fsfsi unsigned short fsi_hvpb; ∕\volume info χ \wedge file system dependent - file search parameters Xstruct fsfsd χ char fsd_work[24] /\work area

Note: The pointers to these structures are not guaranteed to be constant throughout their existance. The FSD should not keep internal pointers to these structures since the data may be moved.

Existing file systems that conform to the Standard Application Program Interface (Standard API) described in this section, may not necessarily support all the described information kept on a file basis. When this is the case, file system drivers are required to return to the application a null (zero) value for the unsupported parameter (when the unsupported data are a subset of the data returned by the API) or to return a ERROR_NOT_SUPPORTED error (when all of the data returned by the API is unsupported).

Time Stamping

All time stamps on files are stamped and propagated to other SFTs when the file is closed or commited (flushed). If a file is opened at time 1, written to at time 2, and closed at time 3, the last write time will be time 3. Subdirectories only have creation time stamps.

The sfi_tstamp field of the file instance structure sffsi contains six flags:

| ST_SCREAT | EQU | 1 | ; stamp creation time |
|-----------|-----|----|-----------------------------|
| ST_PCREAT | EQU | 2 | ; propagate creation time |
| ST_SWRITE | EQU | 4 | ; stamp last write time |
| ST_PWRITE | EQU | 8 | ; propagate last write time |
| ST_SREAD | EQU | 16 | ; stamp last read time |
| ST_PREAD | EQU | 32 | ; propagate last read time |
| | | | |

These flags are cleared when an SFT is created, and some of them may eventually be set by a file system worker routine. They are examined when the file is closed or flushed.

For each time stamp, there are three meaningful actions:

| ST_Sxxx | ST_Pxxx | Action |
|---------|---------|--|
| clear | clear | don't do anything |
| set | set | stamp and propagate (to other SFTs and disk) |
| clear | set | don't stamp, but propagate existing value |

FSD Calling Conventions and Requirements

Calling conventions between FS router, FSD, and FS helpers are:

Arguments will be pushed in left-to-right order onto the stack.

The callee is responsible for cleaning up the stack.

Registers DS, SI, DI, BP, SS, SP are preserved.

Return conditions appear in AX with the convention that AX == 0 indicates successful completion. AX != 0 indicates an error with the value of AX being the error code.

Interrupts must ALWAYS be enabled and the direction flag should be presumed to be undefined. Calls to the FS helpers will change the direction flag at will.

In OS/2, file system drivers are always called in kernel protect mode. This has the advantage of allowing the FSD to execute code without having to account for preemption; no preemption occurs when in kernel mode. While this greatly simplifies FSD structure, it forces the FSD to yield the CPU when executing long segments of code. In particular, an FSD must not hold the CPU for more than 2 milliseconds at a time. The FSD helper FSH_YIELD is provided so that FSDs may relinquish the CPU.

File system drivers cannot have any interrupt-time activations. Because they occupy high, movable, and swappable memory, there is no guarantee of address-ability of the memory at interrupt time.

Each FS service routine may block.

Error Codes

FSDs should use existing error codes when possible. New error codes must be in the range reserved for FSDs. The FS_FSCTL interface must support returning information about new error codes. Unfortunately, no current base applications support retrieving and displaying new error code information. Consequently, new error codes should be restricted to situations where they will only be returned to FSD aware programs. Hopefully in the future the extension of return codes will be supported by the user interface code.

The set of error codes for errors general to all FSDs is 0xEE00 - 0xEEFF. The following errors have been defined:

ERROR_VOLUME_NOT_MOUNTED = 0xEE00 - the FSD did not recognize the volume.

The set of error codes which are defined by each FSD is 0xEF00 - 0xFEFF.

Chapter 2. FS Service Routines

The following table summarizes the entry points that make up the interface between the kernel and the FSD.

| Note: | Names must be in al | l upper case, as | required by | OS/2 naming conventions. |
|-------|---------------------|------------------|-------------|--------------------------|
| | | | | |

| FS Entry Point | Description | FSDs Required to export |
|----------------------|------------------------------------|-------------------------|
| FS_ALLOCATEPAGESPACE | Adjust the size of paging file | PAGE I/O |
| FS_ATTACH | Attach to an FSD | ALL |
| FS_CANCELLOCKREQUEST | Cancel file record lock request | FILE I/O |
| FS_CHDIR | Change/Verify directory path | ALL |
| FS_CHGFILEPTR | Move a file's position pointer | ALL |
| FS_CLOSE | Release a file handle | ALL |
| FS_COMMIT | Flush a file's buffer to disk | ALL |
| FS_COPY | Copy a file | ALL |
| FS_DELETE | Delete a file | ALL |
| FS_DOPAGEIO | Perform paging I/O operations | PAGE I/O |
| FS_EXIT | End of a process cleanup | ALL |
| FS_FILEATTRIBUTE | Query/Set file's attributes | ALL |
| FS_FILEINFO | Query/Set file's information | ALL |
| FS_FILEIO | Multi-function file I/O | FILE I/O |
| FS_FILELOCKS | Request a file record lock/unlock | ALL |
| FS_FINDCLOSE | Directory search close | ALL |
| FS_FINDFIRST | Find first matching filename | ALL |
| FS_FINDFROMNAME | Find matching filename from name | ALL |
| FS_FINDNEXT | Find next matching filename | ALL |
| FS_FINDNOTIFYCLOSE | Close FindNotify handle | ALL |
| FS_FINDNOTIFYFIRST | Monitor a directory for changes | ALL |
| FS_FINDNOTIFYNEXT | Resume reporting directory changes | ALL |
| FS_FLUSHBUF | Commit file buffers to disk | ALL |
| FS_FSCTL | File system control | ALL |
| FS_FSINFO | Query/Set file system information | ALL |
| FS_INIT | FSD initialization | ALL |
| FS_IOCTL | I/O device control | ALL |
| FS_MKDIR | Make a directory | ALL |
| FS_MOUNT | Mount/unmount volumes | ALL |
| FS_MOVE | Move a file or subdirectory | ALL |
| FS_NEWSIZE | Change a file's logical size | ALL |
| FS_NMPIPE | Do a named pipe operation | ALL |
| FS_OPENCREATE | Open/create/replace files | ALL |
| FS_OPENPAGEFILE | Create paging file and handle | PAGE I/O |
| FS_PATHINFO | Query/Set a file's information | ALL |
| FS_PROCESSNAME | FSD unique name canonicalization | ALL |
| FS_READ | Read data from a file | ALL |
| FS_RMDIR | Remove a subdirectory | ALL |
| FS_SETSWAP | Notification of swapfile ownership | ALL |
| FS_SHUTDOWN | Shutdown file system | ALL |
| FS_VERIFYUNCNAME | Verify UNC server ownership | UNC |
| FS_WRITE | Write data to a file | ALL |

Each FS entry point has a distinct parameter list composed of those parameters needed by that particular entry. Parameters include:

File pathname

Current disk/directory information

Open file information

Application data buffers

Descriptions of file extended attributes

Other parameters specific to an individual call

Most of the FS entry points have a level parameter for specifying the level of information they are provided or have to supply. FSDs must provide for additional levels which may be added in future versions of OS/2 by returning ERROR_NOT_SUPPORTED for any level they do not recognize.

File system drivers which support hierarchical directory structures must use '\' and '/' as path name component separators. File system drivers which do not support hierarchical directory structures must reject as illegal any use of '\' or '/' in path names. The file names '.' and '..' are reserved for use in hierarchical directory structures for the current directory and the parent of the current directory, respectively.

Unless otherwise specified in the descriptions below, data buffers may be accessed without concern for the accessibility of the data. OS/2 will either check buffers for accessability and lock them, or transfer them into locally accessible data areas.

Simple parameters will be verified by the IFS router before the FS service routine is called.

Note: New with 2.0, some entry points need only be exported and supported by those FSDs which desire to service the pager(PAGE I/0), UNC servers(UNC) and/or file locking(FILE I/O). With these new entry point groups, a FSD must export all or none of the entry points within a particular group.

These optional entry points are:

FS_AllocatePageSpace(PAGE I/O)FS_CancelLockRequest(FILE I/O)FS_DoPageIO(PAGE I/O)FS_FileLocks(FILE I/O)FS_OpenPageFile(PAGE I/O)FS_VerifyUNCName(UNC)

FS_ALLOCATEPAGESPACE Adjust the size of paging file

Purpose

Changes the size the paging file on disk.

Calling Sequence

int far pascal FS_ALLOCATEPAGESPACE (psffsi, psffsd, ulsize,

ulWantContig)

struct sffsi far \psffsi;struct sffsd far \psffsd;unsigned longulsize;unsigned longulWantContig;

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

ulsize

is the desired new size of the paging file. If the new size is smaller than the current size, the excess space is released. If the new size is larger than the current size, the requested size is allocated.

ulWantContig

indicates the mimimum contiguity requirement (in bytes).

Remarks

ulWantContig is a demand for contiguity. If ulWantContig is non-zero(0), the FSD must allocate any space in the swap file that is not contigous in ulWantContig chunks on ulWantContig boundaries. If it is not possible to grow the file to ulSize bytes meeting the ulWantContig requirement, the operation should fail. If the file is being shrunk ulWantContig is irrelevent and should be ignored.

FSDs that support the paging I/O interface should be expected to be sensible in allocating page space. In particular, they are expected to always attempt to allocate space such that ulWantContig sized blocks on ulWantContig boundaries are physically contigous on disk, and to keep the page file as a whole contigous as possible.

FS_ATTACH Attach to an FSD

Purpose

Attach or detach a remote drive or pseudo-device to an FSD.

Calling Sequence

int far pascal FS_ATTACH (flag, pDev, pvpfsd, pcdfsd, pParm, pLen)

 unsigned short
 flag;

 char far \
 pDev;

 struct vpfsd far \
 pvpfsd;

 struct cdfsd far \
 pcdfsd;

 char far \
 pParm;

 unsigned short far \
 pLen;

Where

flag

indicates attach or detach:

flag == FSA_ATTACH (0x00) requests an attach. The FSD is being called to attach a specified driver or character device.

flag == FSA_DETACH (0x01) requests a detach.

flag == FSA_ATTACH_INFO (0x02) requests the FSD to fill in the specified buffer with attachment information.

pDev

is a pointer to the ASCIIZ text of either the driver (driver letter followed by a colon) or to the character device (must be \DEV\device) that is being attached, detached, or queried. The FSD does not need to verify this pointer.

pvpfsd

is a pointer to a data structure containing file-system-dependent volume parameter information. When an attach/detach/query of a character device is requested, this pointer is null. When attaching a drive, this structure contains no data and is available for the FSD to store information needed to manage the remote drive. All subsequent FSD calls have access to the hVPB in one of the structures passed in, so the FSD has access to this structure by using FSH_GETVOLPARMS. This structure will have its contents as the FSD had left them. When detaching or querying a drive, this structure contains the data as the FSD left them.

pcdfsd

is a pointer to a data structure containing file-system dependent working directory information for drives. When attaching a drive, this structure contains no data and is available for the FSD to store information needed to manage the working directory. All subsequent FSD calls generated by API calls that reference this drive are passed a pointer to this structure with contents left as the FSD left them. When detaching or querying a drive, this structure contains the data as the FSD left them. For character devices, pcdfsd points to a DWORD. When a device is attached, the DWORD contains no data, and can be used by the FSD to store a reference to identify the device later on during FS_OPENCREATE, when it is passed in to the FSD. When detaching or querying the device, this DWORD contains the data as the FSD left them. When the FSD is notified of a detach, it should deallocate any resources allocated for this structure.

Note: The FSD should not expect this pointer to remain constant for the duration of the attach. The contents of the structure will be valid, but the location may change.

pParm

is the address of the application parameter area.

When an attach is requested, this will point to the API-specified user data block that contains information regarding the attach operation (for example, passwords). For a query, the OS/2 kernel will fill in part of the buffer, adjust the pointer, and call the FSD to fill in the rest. (See structure returned by DosQFSAttach; pParm will point to cbFSAData; the FSD should fill in cbFSAData and rgFSAData.)

Addressing of this data area is not validated by the OS/2 kernel. pParm must be verified, even in the query case. The FSD verifies this parameter by calling the FS helper routine FSH_PROBEBUF.

pLen

is the pointer to the length of the application parameter area.

For attach, this points to the length of the application data buffer. For query, this is the length of the remaining space in the application data buffer. Upon filling in the buffer, the FSD will set this to the length of the data returned. If the data returned is longer than the data buffer length, the FSD sets this value to be the length of the data that query could return. In this case, the FSD should also return a BUFFER OVERFLOW error.

The FSD does not need to verify this pointer.

Remarks

Local FSDs will never get called with attempts to attach, detach or query drives.

For remote FSDs called to do a detach, the kernel does not do any checking to see if there are any open references on the drive (for example, open or search references). It is entirely up to the FSD to decide whether it should allow the detach operation.

FS_CANCELLOCKREQUEST Cancel file record lock request

Purpose

Cancels an outstanding FS_FileLocks request on a file.

Calling Sequence

int far pascal FS_CANCELLOCKREQUEST (psffsi, psffsd, pLockRange)

 struct sffsi far \
 psffsi;

 struct sffsd far \
 psffsd;

 struct filelock far \
 pLockRange;

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

pLockRange

is a pointer to a filelock structure. The filelock structure has the following format:

```
struct FileLock {
```

```
unsigned long FileOffset; //offset where the lock/unlock begins X unsigned long RangeLength; //length of region locked/unlocked X }
```

Remarks

This entry point was added to support the 32-bit DosCancelLockRequest API.

This function provides a simple mechanism for cancelling the lock range request of an outstanding FS_FILELOCKS call. If two threads in a process are blocked on a lock range and a cancel request is issued by another thread, both blocked threads will be released.

FS_CHDIR Change/Verify Directory Path

Purpose

Change or verify the directory path for the requesting process

Calling Sequence

int far pascal FS_CHDIR (flag, pcdfsi, pcdfsd, pDir, iCurDirEnd)

| unsigned short | flag; |
|--------------------|-------------|
| struct cdsfi far \ | pcdfsi; |
| struct cdfsd far \ | pcdfsd; |
| char far \ | pDir; |
| unsigned short | iCurDirEnd; |

Where

flag

indicates what action is to be taken on the directory.

flag == CD_EXPLICIT (0x00) indicates that an explicit directory-change request has been made.

flag == CD_VERIFY (0x01) indicates that the working directory needs to be verified.

flag == CD_FREE (0x02) indicates that this reference to a directory is being freed.

The flag passed to the FSD will have a valid value.

pcdfsi

is a pointer to a file-system-independent working directory structure.

For flag == 0, this pointer points to the previous current directory on the drive.

For flag == 1, this pointer points to the most-recent working directory on the drive. The cdi_curdir field contains the text of the directory that is to be verified.

For flag == 2, this pointer is null.

The FSD must never modify the cdfsi. The OS/2 kernel handles all updates.

pcdfsd

is a pointer to a file-system-dependent working directory structure.

This is a place for the FSD to store information about the working directory. The FSD is expected to update this information if the directory exists. The cdfsd pointer is always valid upon entry. If the current directory is the root directory, the contents of this area is undefined. Otherwise, the information is the information that was left there by the FSD.

pDir

is a pointer to directory text.

For flag == 0, this is the pointer to the directory. For flag == 1 or flag == 2, this pointer is null. The FSD does not need to verify this pointer.

iCurDirEnd

is the index of the end of the current directory in pDir.

This is used to optimize FSD path processing. If iCurDirEnd == -1, there is no

current directory relevant to the directory text, that is, a device. This parameter only has meaning for flag == 0.

Remarks

The FSD should cache no information when the directory is the root. Root directories are a special case. They always exist, and never need validation. The OS/2 kernel does not pass root directory requests to the FSD. An FSD is not allowed to cache any information in the cdfsd data structure for a root directory. Under normal conditions, the kernel does not save the CDS for a root directory and builds one from scratch when it is needed. (One exception is where a validate CDS fails, and the kernel sets it to the root, and zeroes out the cdfsd data structure. This CDS is saved and is cleaned up later.)

The following is information about the exact state of the cdfsi and cdfsd data structures passed to the FSD for each flag value and guidelines about what an FSD should do upon receiving an FS_CHDIR call:

IF (flag == 0) \land Set new Current Directory &

pcdfsi, pcdfsd = copy of CDS we're starting from; may be useful as starting point for verification.

cdfsi contents:

hVPB - handle of Volume Parameter Block mapped to this drive

end - end of root portion of CurDir

flags - various flags (indicating state of cdfsd)

IsValid - cdfsd is unknown format (ignore contents) IsValid == 0x80

IsRoot - cdfsd is meaningless if CurDir = root (not kept) IsRoot == 0x40

IsCurrent - cdfsd is know format, but may not be current (medium may have been changed). IsCurrent == 0x20

text - Current Directory Text

icurdir = if Current Directory is in the path of the new Current Directory, this is the index to the end of the Current Directory. If not, this is -1 (Current Directory does not apply).

pDir = path to verify as legal directory

THEN

Validate path named in pDir. \[AThis means both that it exists AND that it is a directory. pcdfsi, pcdfsd, icurdir give old CDS, which may allow optimization \[X]

IF (Validate succeeds) IF (pDir != ROOT) Store any cache information in area pointed to by pcdfsd. ELSE Do Nothing. ∧Area pointed to by pcdfsd will be thrown away, so don't bother storing into it X Return success. ELSE

Return failure.

 \land Kernel will create new CDS using pDir data and pcdfsd data. If the old CDS is valid, the kernel will take care of cleaning it up. The FSD must not edit any structure other than the Pcdfsd area, with which it may do as it chooses. \land

 $\wedge flag == 0 \vee$

ELSE

IF (flag == 1) //Validate current CDS structure X

pcdfsi = pointer to copy of cdfsi of interest.

pcdfsd = pointer to copy of cdfsd. Flags in cdfsi indicate the state of this cdfsd. It may be: (1) completely invalid (unknown format), (2) known format, but non-current information, (3) completely valid, or (4) all zero (root).

THEN

Validate that CDS still describes a legal directory (using cdi_text).

IF (valid)

Update cdfsd if necessary. Return success. /kernel will copy cdfsd into real CDS X

ELSE

IF (cdi_isvalid)

Release any resources associated with cdfsd.

- /kernel will force Current Directory to root, and will zero out cdfsd in real CDS ${\tt X}$
- Return failure.
- $\wedge The \ FSD \ must not modify any structure other than the cdfsd pointed to by pcdfsd. <math display="inline">\quad \mbox{\ensuremath{\lambda}}$

ELSE

IF (flag == 2) \land previous CDS no longer in use; being freed &

pcdfsd = pointer to copy of cdfsd of CDS being freed.

THEN

Release any resources associated with the CDS.

 \wedge kernel will not retain the cdfsd \times

FS CHGFILEPTR Move a file's position pointer

Purpose

Move a file's logical read/write position pointer.

Calling Sequence

int far pascal FS_CHGFILEPTR (psffsi, psffsd, offset, type, IOflag)

struct ssfsi far \ psffsi; struct ssfsd far \setminus psffsd; long unsigned short unsigned short

offset; type; IOflag;

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

The FSD uses the current file size or sfi_position along with offset and type to compute a new sfi_position. This is updated by the system.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

The FSD may store or adjust data as appropriate in this structure.

offset

is the signed offset to be added to the current file size or position to form the new position within the file.

type

indicates the basis of a seek operation.

type == CFP_RELBEGIN (0x00) indicates seek relative to beginning of file. type == CFP_RELCUR (0x01) indicates seek relative to current position within the file.

type == CFP_RELEND (0x02) indicates seek relative to end of file.

The value of type passed to the FSD will be valid.

IOflag

indicates information about the operation on the handle.

IOflag == IOFL_WRITETHRU (0x0010) indicates write-through. IOflag == IOFL NOCACHE (0x0020) indicates no-cache.

Remarks

The file system may want to take the seek operation as a hint that an I/O operation is about to take place at the new position and initiate a positioning operation on sequential access media or read-ahead operation on other media.

Some DOS mode programs expect to be able to do a negative seek. OS/2 passes these requests on to the FSD and returns an error for OS/2 mode negative seek requests. Because a seek to a negative position is, effectively, a seek to a very large offset, it is suggested that the FSD return end-of-file for subsequent read requests.

FSDs must allow seeks to positions beyond end-of-file.

The information passed in IOflag is what was set for the handle during a DosOpen/DosOpen2 operation, or by a DosSetFHandState call.

If an FSD supports file locking, it is responsible for checking if there are any locks on the file that should prevent the call from being executed. OS/2 will not do any lock checking if the FSA_LOCK bit is set in the FSD Attributes.

FS_CLOSE Close a file.

Purpose

Closes the specified file handle.

Calling Sequence

int far pascal FS_CLOSE (type, IOflag, psffsi, psffsd)

unsigned short type; unsigned short struct sffsi far \ psffsi; struct sffsd far \ psffsd;

IOflag;

Where

type

indicates what type of a close operation this is.

type == FS_CL_ORDINARY (0x00) indicates that this is not the final close of the file or device.

type == FS CL FORPROC (0x01) indicates that this is the final close of this file or device for this process.

type == FS_CL_FORSYS (0x02) indicates that this is the final close for this file or device for the system.

IOflag

indicates information about the operation on the handle.

IOflag == IOFL WRITETHRU (0x0010) indicates write-through. IOflag == IOFL_NOCACHE (0x0020) indicates no-cache.

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

Remarks

This entry point is called on every close of a file or device.

Any reserved resources for this instance of the open file may be released. It may be assumed that all open files will be closed at process termination. That is, this entry point will always be called at process termination for any files or devices open for the process.

A close operation should be interpreted by the FSD as meaning that the file should be commited to disk as appropriate.

Of the information passed in IOflag, the write-through bit is a mandatory bit in that any data written to the block device must be put out on the medium before the FSD returns. The no-cache bit, on the other hand, is an advisory bit that says whether the data being transferred is worth caching or not.

FS_COMMIT Commit a file's buffers to Disk

Purpose

Flush requesting process's cache buffers and update directory information for the file handle.

Calling Sequence

int far pascal FS_COMMIT (type, IOflag, psffsi, psffsd)

unsigned short type; unsigned short IOflag; struct sffsi far \ psffsi; struct sffsd far\ psffsd;

Where

type

indicates what type of a commit operation this is.

type == FS_COMMIT_ONE (0x01) indicates that this is a commit for a specific handle. This type is specified if FS_COMMIT is called for a DosBufReset of a specific handle.

```
type == FS_COMMIT_ALL (0x02) indicates that this is a commit due to a DosBufReset (-1).
```

lOflag

indicates information about the operation on the handle.

IOflag == IOFL_WRITETHRU (0x0010) indicates write-through. IOflag == IOFL NOCACHE (0x0020) indicates no-cache.

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

Remarks

This entry point is called only as a result of a DosBufReset function call. OS/2 reserves the right to call FS_COMMIT even if no changes have been made to the file.

For DosBufReset (-1), FS_COMMIT will be called for each open handle on the FSD.

The FSD should update access and modification times, if appropriate.

Any locally cached information about the file must be output to the media. The directory entry for the file is to be updated from the sffsi and sffsd data structures.

Since mini-FSDs used to boot IFSs are read-only file systems, they need not support the FS_COMMIT call.

Of the information passed in IOflag, the write-through bit is a MANDATORY bit in that any data written to the block device must be put out on the medium before the

FSD returns. The no-cache bit, on the other hand, is an advisory bit that says whether the data being transferred is worth caching or not.

The FSD should copy all supported time stamps from the SFT to the disk. Beware that the last read time stamp may need to be written to the disk even though the file is clean. After this is done, the FSD should clear the sfi_tstamp field to avoid having to write to the disk again if the user calls commit repeatedly without changing any of the time stamps.

If the disk is not writeable and only the last read time stamp has changed, the FSD should either issue a warning or ignore the error. This relieves the user from having to un-protect an FSD floppy disk in order to read the files on it.

FS_COPY Copy a file

Purpose

Copy a specified file or subdirectory to a specified target.

Calling Sequence

int far pascal FS_COPY (flag, pcdfsi, pcdfsd,

pSrc, iSrcCurDirEnd, pDst, iDstCurDirEnd, nameType)

unsigned shortflag;struct cdfsi far \pcdfsi;struct cdfsd far \pcdfsd;char far \pSrc;unsigned short iSrcCurDirEnd;char far \char far \pDst;unsigned short iDstCurDirEnd;unsigned short iDstCurDirEnd;

Where

flag

is a bit mask controlling copy

0x0001 specifies that an existing target file/directory should be replaced 0x0002 specifies that a source file will be appended to the destination file. All other bits are reserved.

(See the description of the DosCopy function call in the OS/2 Version 3.0 Control Program Programming Reference.)

pcdfsi

is a pointer to the file-system-independent working directory structure.

pcdfsd

is a pointer to the file-system-dependeng working directory structure.

pSrc

is a pointer to the ASCIIZ name of the source file/directory.

iSrcCurDirEnd

is the index of the end of the current directory in pSrc. If = -1, there is no current directory relevant to the source name.

pDst

is a pointer to the ASCIIZ name of the destination file/directory.

iDstCurDirEnd

is the index of the end of the current directory in pDst. If = -1, there is no current directory relevant to the destination name.

nameType

indicates the destination name type.

NameType == 0x0040 indicates non-8.3 filename format. All other values are reserved.

Remarks

The file specified in the source file name should be copied to the target file if possible.

The files specified may not be currently open. File system drivers must assure consistency of file allocation information and directory entries.

The file system driver returns the special CANNOT COPY error if it cannot perform the copy because:

it does not know how

the source and target are on different volumes

of any other reason for which it would make sense for its caller to perform the copy operation manually.

Returning ERROR_CANNOT_COPY indicates to its caller that it should attempt to perform the copy operation manually. Any other error will be returned directly to the caller of DosCopy. Currently, the manual copy is performed in the DOSCALL1.DLL if ERROR_CANNOT_COPY is returned. Although support of this functions is not required beyond the return code of ERROR_CANNOT_COPY, it is encouraged due to the significant performance improvement copying within the FSD. See the description of the DosCopy function call in the *OS/2 Version 3.0 Control Program Programming Reference* for other error codes that can be returned.

FS_COPY needs to check that certain types of illegal copying operations are not performed. A directory cannot be copied to itself or to one of its subdirectories. This is especially critical in situations where two different fully-qualified pathnames can refer to the same file or directory. For example, if X: is redirected to \\SERVER\SHARE, the X:\PATH and \\SERVER\SHARE\PATH refer to the same object.

The behavior of FS_COPY should match the behavior of the generic DosCopy routine.

The non-8.3 filename format attribute in the directory entry for the destination name should be set according to the value in nameType.

FS_DELETE Delete a file

Purpose

Removes a directory entry associated with a filename.

Calling Sequence

int far pascal FS_DELETE (pcdfsi, pcdfsd, pFile, iCurDirEnd)

Where

pcdfsi

is a pointer to the file-system-independent working directory structure.

pcdfsd

is a pointer to the file-system-dependent working directory structure.

pFile

is a pointer to the ASCIIZ name of the file or directory. The FSD does not need to validate this pointer.

iCurDirEnd

is the index of the end of the current directory in pFile.

This is used to optimize FSD path processing. If iCurDirEnd == -1, there is no current directory relevant to the name text, that is, a device.

Remarks

The file specified is deleted.

The deletion of a file opened in DOS mode by the same process requesting the delete is supported. OS/2 calls FS_CLOSE for the file before calling FS_DELETE.

The file name may not contain wildcard characters.

FS_DOPAGEIO Perform paging I/O operations

Purpose

Performs all the I/O operations in a PageCmdList.

Calling Sequence

int far pascal FS_DOPAGIO (psffsi, psffsd, pList)

struct sffsi far \ psffsi; struct sffsd far \ psffsd; struct PageCmdHeader far \ pList;

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

pList

is a pointer to a PageCmdHeader structure. The PageCmdHeader structure has the following format:

struct PageCmdHeader {

| | U | C C | | | | |
|---|--|----------------|--------------------|---|---|--------|
| | unsigned char | InFlags; | ∧Input | Flags | Х | |
| | unsigned char | OutFlags; | ∕∖Outpu | It Flags - must be 0 on entry X | | |
| | unsigned char | OpCount; | ∕∖Nun | nber of operations | Х | |
| | unsigned char | Pad; | ∧Pad t | for DWORD alignment |) | (|
| | unsigned long | Reserved1; | ∕∖Curre | ently Unused | Х | |
| | unsigned long | Reserved2; | ∕∖Curre | ently Unused | Х | |
| | unsigned long | , | | ently Unused | Х | |
| | struct PageCmd | , | | ently Unused | Х | |
| } | ∧FSD_DoPagel #define PGIO_1 | 0 | es X Əx01 | ∧Force Order of operations | Х | |
| | ∧FSD_DoPagel | O OutFlags val | ues X | | | |
| | #define PGIO_ | FO_DONE | 0x01 | \wedge Operation done | | Х |
| | #define PGIO_] | FO_ERROR | 0x02 | ∧Operation failed | Х | |
| | <pre> /FSD_DoPagel #define PGIO_4 #define PGIO_4</pre> | ATTEMPTED | xX 0x0f 0xf0 | ∧Operation attempted ∧Operation failed | | X X |
| | | | | | | |

The PageCmd structure has the following format:

| <pre>struct PageCmd {</pre> | | | |
|-----------------------------|-------------|--|---|
| unsigned char | Cmd; | ∧Cmd Code (Read,Write,Verify) | Х |
| unsigned char | Priority; | \land Same values as for req packets \land | |
| unsigned char | Status; | ∧Status byte | Х |
| unsigned char | Error; | ∧I24 error code | Х |
| unsigned long | Addr; | \land Physical(0:32) or Virtual(16:16) \land | |
| unsigned long | FileOffset; | \land Byte Offset in page file \land | |
| } | | | |

Remarks

FS_DOPAGEIO performs all the I/O operations specified in the PageCmdList.

If the disk driver supports Extended Strategy requests, a request list will be built from the PageCmdList and issued to the driver.

If the disk driver does not support Extended Strategy requests, the FSD can either let the kernel do the emulation(See FS_OPENPAGEFILE to set this state) or has the option to do the emulation itself.

For a detailed description of the Extended Strategy request interface please see the *OS/2 Version 3.0 Physical Device Driver Reference*.

FS_EXIT End of process

Purpose

Release FSD resources still held after process termination.

Calling Sequence

void far pascal FS_EXIT (uid, pid, pdb);

unsigned short uid; unsigned short pid; unsigned short pdb;

Where

uid

is the user ID of the process. This will be a valid value.

pid

is the process ID of the process. This will be a valid value.

pdb

is the DOS mode process ID of the process. This will be a valid value.

Remarks

Because all files are closed when a process terminates, this call is not needed to release file resources. It is, however, useful if resources are being held due to unterminated searches (as in searches initiated from the DOS mode). If an FSD allocates resources every time an FS_FINDFIRST sequence is entered, resource shortages can occur under DOS since DOS programs do not have a DosFindClose API. This entry point provides a way for an FSD to determine that those resources may be released.

FS_FILEATTRIBUTE Query/Set File Attribute

Purpose

Query/Set the attribute of the specified file.

Calling Sequence

int far pascal FS_FILEATTRIBUTE (flag, pcdfsi, pcdfsd,

pName, iCurDirEnd, pAttr)

| unsigned short | flag; |
|------------------------|-------------|
| struct cdfsi far \ | pcdfsi; |
| struct cdfsd far \ | pcdfsd; |
| char far \setminus | pName; |
| unsigned short | iCurDirEnd; |
| unsigned short far $\$ | pAttr; |

Where

flag

indicates retrieval or setting of attributes, with:

flag == FA_RETRIEVE (0x00) indicates retrieving the attribute. flag == FA_SET (0x01) indicates setting the attribute. flag == all other values, reserved.

The value of flag passed to the FSD will be valid.

pcdfsi

is a pointer to the file-system independent portion of an open file instance.

pcdfsd

is a pointer to the file-system dependent portion of an open file instance.

pName

is a pointer to the ASCIIZ name of the file or directory.

The FSD does not need to validate this pointer.

iCurDirEnd

is the index of the end of the current directory in pName.

This is used to optimize FSD path processing. If iCurDirEnd == -1, there is no current directory relevant to the name text, that is, a device.

pAttr

is a pointer to the attribute.

For flag == 0 (Query), the FSD should store the attribute in the indicated location.

For flag == 1 (Set), the FSD should retrieve the attribute from this location and set it in the file or directory.

The FSD does not need to validate this pointer.

Remarks None

FS_FILEINFO Query/Set a File's Information

Purpose

Returns information for a specific file.

Calling Sequence

int far pascal FS_FILEINFO (flag, psffsi, psffsd,

level, pData, cbData, IOflag)

| unsigned short | flag; |
|----------------------|---------|
| struct sffsi far $\$ | psffsi; |
| struct sffsd far $\$ | psffsd; |
| unsigned short | level; |
| char far \setminus | pData; |
| unsigned short | cbData; |
| unsigned short | IOflag; |

Where

flag

indicates retrieval or setting of information.

flag == FI_RETRIEVE (0x00) indicates retrieving information. flag == FI_SET (0x01) indicates setting information. All other values are reserved.

The value of flag passed to the FSD will be valid.

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

level

is the information level to be returned.

Level selects among a series of data structures to be returned.

pData

is the address of the application data area.

Addressing of this data area is validated by the kernel (see FSH_PROBEBUF).

When retrieval (flag == 0) is specified, the FSD will place the information into the buffer.

When outputting information to a file (flag == 1), the FSD will retrieve that data from the application buffer.

cbData

is the length of the application data area.

For flag == 0, this is the length of the data the application wishes to retrieve. If there is not enough room for the entire level of data to be returned, the FSD will return a BUFFER OVERFLOW error.

For flag == 1, this is the length of data to be applied to the file.

IOflag

indicates information about the operation on the handle.

IOflag == IOFL_WRITETHRU (0x0010) indicates write-through. IOflag == IOFL_NOCACHE (0x0020) indicates no-cache.

Remarks

If setting the time/date/DOS attributes on a file:

Copy the new time/date/DOS attributes into the SFT Set ST_PCREAT, ST_PWRITE, and ST_PREAD Clear ST_SCREAT, ST_SWRITE, and ST_SREAD Do not change the file size with this entry point.

Note: ALSO NEW FOR 2.0, it is suggested that the FSD copy the DOS file attributes from the directory entry into the SFT. This allows the FSD and the OS2 kernel to handle FCB opens more efficiently.

If querying the date/time/DOS attributes on a file, simply copy the date/time/DOS attributes from the directory entry into the SFT.

If the attribute value for the date or time is 0 (zero), you should not change the current value, as per the *OS/2 Version 3.0 Control Program Programming Reference*.

Of the information passed in IOflag, the write-through bit is a mandatory bit in that any data written to the block device must be put out on the medium before the device driver returns. The no-cache bit, on the other hand, is an advisory bit that says whether the data being transferred is worth caching or not.

Supported information levels are described in the *OS/2 Version 3.0 Control Program Programming Reference*. However, since the IFS architecture is still 16 Bit, the data structures that the FSD returns are the structures GEA, GEALIST, FEA, FEALIST, and EAOP- not the GEA2, GEA2LIST, etc. (see below). OS/2 will convert the structure to the appropriate 32 Bit form for 32 Bit applications. In addition to the information levels described in the *OS/2 Version 3.0 Control Program Programming Reference* level 4 support is required in all FSDs. For level 4, ignore the GEALIST and return all EAs to the caller in the FEALIST. The external publication of level 4 for 32 bit applications is being considered at this time. This call will not be officially supported for 16 Bit applications since we are hoping in the future to permit extended attributes to exceed 64K and that would break those applications.

| typedef struct _GEA { BYTE cbName; CHAR szName[1]; } GEA; | <pre>/gea \</pre> | | X X |
|---|--|---|-------------|
| typedef struct _GEALIST { ULONG cbList; GEA list[1]; } GEALIST; | <pre>/geal X</pre> | Х | |
| typedef struct _FEA { BYTE fEA; BYTE cbName; USHORT cbValue; } FEA; typedef FEA FAR PFEA; ∧flags for _FEA.fEA X | <pre> /fea X</pre> | | X X X |
| #define FEA_NEEDEA 0x80 | ∧need EA bit X | | |
| typedef struct _FEALIST { ULONG cbList; FEA list[1]; } FEALIST; | <pre>\feal \(\</pre> | Х | |
| typedef struct _EAOP { PGEALIST fpGEAList; PFEALIST fpFEAList; ULONG oError; } EAOP; | ∧eaop X ∧general EA list X ∧full EA list X | | |

Application Note: When an application does a level 3 query, it supplies a list of EA names in the GEALIST that they want the EA values for. If there are no extended attributes for that file, it is legal to return an FEALIST with a cbList equal to 4 and no FEAs. However, there have been applications in the past that have coded assuming that an FEALIST will be returned with a cbValue of 0 if the EA does not exist. If those applications try to access the non-initialized information they will, of course, fail. FSD implementors may avoid future problems by returning the FEALIST with cbValues set to 0 when there are no EAs, but this is not an architectural requirement.

FS_FILEIO Multi-function file I/O

Purpose

Perform multiple lock, unlock, seek, read, and write I/O.

Calling Sequence

int far pascal FS_FILEIO (psffsi, psffsd, pCmdList, cbCmdList, poError, IOflag)

struct sffsi far \ psffsi; struct sffsd far \ psffsd; char far \ pCmdList; unsigned short cbCmdList; unsigned short far \ poError; unsigned short IOflag;

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

pCmdList

is a pointer to a command list that contains entries indicating what commands will be performed.

Each individual operation (CmdLock, CmdUnloc, CmdSeek, CmdIO) is performed as atomic operations until all are complete or until one fails. CmdLock executes a multiple range lock as an atomic operation. CmdUnlock executes a multiple range unlock as an atomic operation. Unlike CmdLock, CmdUnlock cannot fail as long as the parameters to it are correct, and the calling application had done a Lock earlier, so it can be viewed as atomic.

The validity of the user address is not verified (see FSH_PROBEBUF).

For CmdLock, the command format is:

struct CmdLock {
unsigned short Cmd = 0; /0 for lock operations X
unsigned long TimeOut; /ms timeout for lock success X
}

which is followed by a series of records of the following format:

 struct Lock {

 unsigned short Share = 0;
 $\land 0$ for exclusive, 1 for read-only \land

 long
 Start;
 \land start of lock region
 \land

 long
 Length;
 \land length of lock region
 \land

 }

 \land \land

If a lock within a CmdLock causes a timeout, none of the other locks within the scope of CmdLock are in force, because the lock operation is viewed as atomic.

CmdLock.TimeOut is the count in milliseconds, until the requesting process is to resume execution if the requested locks are not available. If

CmdLock.TimeOut == 0, there will be no wait. If CmdLock.TimeOut < 0xFFFFFFF it is the number of milliseconds to wait until the requested locks become available. If CmdLock.TimeOut == 0xFFFFFFFF then the thread will wait indefinitely until the requested locks become available.

Lock.Share defines the type of access other processes may have to the filerange being locked. If its value == 0, other processes have No-Access to the locked range. If its value == 1, other process have Read-Only access to the locked range.

For CmdUnlock, the command format is:

which is followed by a series of records of the following format:

```
struct UnLock {
long Start; /start of locked region X
long Length; /length of locked region X
```

For CmdSeek, the command format is:

| struct Cm | dSeek { | | |
|------------|------------------|---|---|
| unsigned s | short $Cmd = 2;$ | \wedge 2 for seek operation | Х |
| unsigned s | short Method; | $\land 0$ for absolute | Х |
| | | \wedge 1 for relative to current | Х |
| | | \land 2 for relative to EOF | Х |
| long | Position; | \land file seek position or delta \land | |
| long | Actual; | \wedge actual position seeked to | Х |
| } | | | |
| | | | |

For CmdIO, the command format is:

cbCmdList

}

is the length in bytes of the command list.

poError

is the offset within the command list of the command that caused the error.

This field has a value only when an error occurs.

The validity of the user address has not been verified (see FSH_PROBEBUF).

IOflag

indicates information about the operation on the handle.

IOflag == IOFL_WRITETHRU (0x0010) indicates write-through. IOflag == IOFL_NOCACHE (0x0020) indicates no-cache.

Remarks

This function provides a simple mechanism for combining the file I/O operations into a single request and providing improved performance, particularly in a networking environment.

File systems that do not have the FileIO bit in their attribute field do not see this call: The command list is parsed by the IFS router. The FSD sees only FS_CHGFILEPTR, FS_READ, FS_WRITE calls.

File systems that have the FileIO bit in their attribute field see this call in its entirety. The atomicity guarantee applies only to the commands themselves and not to the list as a whole.

Of the information passed in IOflag, the write-through bit is a mandatory bit in that any data written to the block device must be put out on the medium before the device driver returns. The no-cache bit, on the other hand, is an advisory bit that says whether the data being transferred is worth caching or not.

FS_FILELOCKS Request a file record lock/unlock

Purpose

Locks and/or unlocks a range(record) in a opened file.

Calling Sequence

int far pascal FS_FILELOCKS (psffsi, psffsd, pUnLockRange,

pLockRange, timeout, flags)

| struct sffsi far $\$ | psffsi; |
|-------------------------|---------------|
| struct sffsd far $\$ | psffsd; |
| struct filelock far $\$ | pUnLockRange; |
| struct filelock far $\$ | pLockRange; |
| unsigned long | timeout; |
| unsigned long | flags; |

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

pUnLockRange

is a pointer to a filelock structure, identifying the range of the file to be unlocked. The filelock structure has the following format:

```
struct filelock {
```

```
unsigned long FileOffset; \land offset where the lock/unlock begins \land unsigned long RangeLength; \land length of region locked/unlocked \land
```

If RangeLength is zero, no unlocking is required.

pLockRange

is a pointer to a filelock structure, identifying the range of the file to be locked. If RangeLength is zero, no locking is required.

timeout

is the maximum time in milliseconds that the requestor wants to wait for the requested ranges, if they are not immediately available.

flags

specify what actions are to be taken depending on how the flag bits are set.

flags

is the bit mask which specifies what actions are to taken:

SHARE Bit 0 on indicates other processes can share access to this locked range. Ranges with SHARE bit on can overlap.

SHARE Bit 0 off indicates the current process has exclusive access to the locked range. An range with the SHARE bit off CANNOT overlap with any other lock range.

ATOMIC Bit 1 on indicates an atomic lock request. If the lock range equals the unlock range, an atomic lock will occur. If the ranges are not equal, an error will be returned.

All other bits(2-31) are reserved and must be zero.

Remarks

This entry point was added to support the 32-bit DosSetFileLocks API.

If the lock and unlock range lengths are both zero, an error,

ERROR_LOCK_VIOLATION will be returned to the caller. If only a lock is desired, pUnLockRange can be NULL or both FileOffset and RangeLength should be set to zero when the call is made. The opposite is true for an unlock.

When the atomic bit is not set, the unlock occurs first then the lock is performed. If an error occurs on the unlock, an error is returned and the lock is not performed. If an error occurs on the lock, an error is returned and the unlock remains in effect if one was requested. If the atomic bit is set and the unlock range equals the lock range and the unlock range has shared access but wants to change the access to exclusive access, the function is atomic. FSDs may not support atomic lock functions. If error ERROR_ATOMIC_LOCK_NOT_SUPPORTED is returned, the application should do an unlock and lock the range using non-atomic operations. The application should also be sure to refresh its internal buffers prior to making any modifications.

Closing a file with locks still in force causes the locks to be released in no defined order.

Terminating a process with a file open and having issued locks on that file causes the file to be closed and the locks to be released in no defined order.

The figure below describes the level of access granted when the accessed region is locked. The locked regions can be anywhere in the logical file. Locking beyond end-of-file is not an error. It is expected that the time in which regions are locked will be short. Duplicating the handle duplicates access to the locked regions. Access to the locked regions is not duplicated across the DosExecPgm system call. The proper method for using locks is not to rely on being denied read or write access, but attempting to lock the region desired and examining the error code.

| Locked Access Table | | | |
|---------------------|------------------------|------------------------|--|
| Action | Exclusive Lock | Shared Lock | |
| Owner read | Success | Success | |
| Non-owner read | Return code, not block | Success | |
| Owner write | Success | Return code, not block | |
| Non-owner write | Return code, not block | Return code, not block | |

The locked access table has the actions on the left as to whether owners or nonowners of a file do either reads or writes of files that have exclusive or shared locks set. A range to be locked for exclusive access must first be cleared of any locked subranges or locked any locked subranges or locked overlapping ranges.

FS_FINDCLOSE Directory Read (Search) Close

Purpose

Provides the mechanism for an FSD to release resources allocated on behalf of FS_FINDFIRST and FS_FINDNEXT.

Calling Sequence

int far pascal FS_FINDCLOSE (pfsfsi, pfsfsd)

struct fsfsi far \pfsfsi;struct fsfsd far \pfsfsd;

Where

pfsfsi

is a pointer to the file-system-independent file search structure.

The FSD should not update this structure.

pfsfsd

is a pointer to the file-system-dependent file search structure.

The FSD may use this to store information about continuation of its search.

Remarks

DosFindClose has been called on the handle associated with the search buffer. Any file system related information may be released.

If FS_FINDFIRST for a particular search returns an error, an FS_FINDCLOSE for that search will not be issued.

FS_FINDFIRST Find First Matching File Name(s)

Purpose

Find first occurrence(s) of matching file name(s) in a directory.

Calling Sequence

int far pascal FS_FINDFIRST (pcdfsi, pcdfsd, pName, iCurDirEnd,

attr, pfsfsi, pfsfsd, pData, cbData, pcMatch, level, flags)

struct cdfsi far \ pcdfsi; struct cdfsd far \setminus pcdfsd; char far \ pName; unsigned short iCurDirEnd; unsigned short attr; struct fsfsi far \ pfsfsi; struct fsfsd far \ pfsfsd; char far \setminus pData; unsigned short cbData; unsigned short far \pcMatch; unsigned short level: unsigned short flags;

Where

pcdfsi

is a pointer to the file-system-independent working directory structure.

pcdfsd

is a pointer to the file-system-dependent working directory structure.

pName

is a pointer to the ASCIIZ name of the file or directory.

Wildcard characters are allowed only in the last component. The FSD does not need to validate this pointer.

iCurDirEnd

is the index of the end of the current directory in pName.

This is provided to allow optimization of FSD path processing. If iCurDirEnd == -1 there is no current directory relevant to the name text, that is, a device.

attr

is a bit field that governs the match.

Any directory entry whose attribute bit mask is a subset of attr and whose name matches that in pName should be returned. The attr field is two byte sized attribute bit masks. The least significant byte contains the "may have" bits. For example, a "may have" attribute of system and hidden is passed in. A file with the same name and an attribute of system is found. This file is returned. A file with the same name and no attributes (a regular file) is also returned. The "may have" attributes read-only and file-archive will not be passed in and should be ignored when comparing directory attributes. The most significant byte contains the "must have" bits. A file with a matching name must also have the attributes in the "must have" bits to be returned. See the *OS/2 Version 3.0 Control Program Programming Reference* for more information about the attribute field under DosFindFirst.

The value of attr passed to the FSD will be valid. The bit 0x0040 indicates a non-8.3 filename format. It should be treated the same way as system and hidden attributes are. You should not return a file name that does not conform to 8.3 filename format if this bit is not set in the "may have" bits.

pfsfsi

is a pointer to the file-system-independent file-search structure.

The FSD should not update this structure.

pfsfsd

is a pointer to the file-system-dependent file-search structure.

The FSD may use this to store information about continuation of the search.

pData

is the address of the application data area.

Addressing of this data area is not validated by the kernel (see FSH_PROBEBUF). The FSD will fill in this area with a set of packed, variable-length structures that contain the requested data and matching file name.

cbData

is the length of the application data area in bytes.

pcMatch

is a pointer to the number of matching entries.

The FSD returns, at most, this number of entries; the FSD returns in this parameter the number of entries actually placed in the data area.

The FSD does not need to validate this pointer.

level

is the information level to be returned.

Level selects among a series of data structures to be returned (see below). The level passed to the FSD is valid.

flags

indicates whether to return file-position information.

- flags == FF_NOPOS (0x00) indicates that file-position information should not be returned (see below).
- flags == FF_GETPOS (0x01) indicates that file-position information should be returned and the information format described below should be used.

The flag passed to the FSD has a valid value.

Remarks

Note:

The find structure passed back to the user is the structure defined for the 16 bit DosFindFirst API with some modification if the flags parameter is set. The basic, level one FILEFINDBUF structure is

| struct FileFindBuf { | | | | |
|----------------------|-------------|--|--|--|
| unsigned short | dateCreate; | | | |
| unsigned short | timeCreate; | | | |
| unsigned short | dateAccess; | | | |
| unsigned short | timeAccess; | | | |
| unsigned short | dateWrite; | | | |
| unsigned short | timeWrite; | | | |
| long | cbEOF; | | | |
| long | cbAlloc; | | | |
| unsigned short | attr; | | | |
| unsigned char | cbName; | | | |
| unsigned char | szName[]; | | | |
| } | | | | |

For flags == 1, the FSD must store in the first DWORD of the per-file attributes structure adequate information that in addition with the file name will allow the search to be resumed from the file by calling FS_FINDFROMNAME. For example, an ordinal representing the file's position in the directory could be stored. If the filename must be used to restart the search, the DWORD may be left blank.

For level 0x0001 and flags == 1, directory information for FS_FINDFIRST is returned in the following format:

| struct FileF | romFi | ndBuf { | | |
|--------------|-------|-------------|--|---|
| long | | position; | \land position given to FSD on following \land | |
| | | | /\FS_FINDFROMNAME call | Х |
| unsigned | short | dateCreate; | | |
| unsigned | short | timeCreate; | | |
| unsigned | short | dateAccess; | | |
| unsigned | short | timeAccess; | | |
| unsigned | short | dateWrite; | | |
| unsigned | short | timeWrite; | | |
| long | | cbEOF; | | |
| long | | cbAlloc; | | |
| unsigned | short | attr; | | |
| unsigned | char | cbName; | | |
| unsigned | char | szName[]; | | |
| } | | | | |

The other information levels have similar format, with the position the first field in the structure for flags == 1. For level 0x0002 and flags == 1, directory information for FS_FINDFIRST is returned in the following format:

| struct FileFromFi | ndBuf { | | | |
|-------------------|-------------|---|---|---|
| long | position; | \wedge this field is not present if flags \land | | |
| | | ∕\is 0 | | Х |
| unsigned short | dateCreate; | | | |
| unsigned short | timeCreate; | | | |
| unsigned short | dateAccess; | | | |
| unsigned short | timeAccess; | | | |
| unsigned short | dateWrite; | | | |
| unsigned short | timeWrite; | | | |
| long | cbEOF; | | | |
| long | cbAlloc; | | | |
| unsigned short | attr; | | | |
| unsigned long | cbList; / | \size of EAs for the file | Х | |
| unsigned char | cbName; | | | |
| unsigned char | szName[]; | | | |
| } | | | | |

For level 0x0003 and flags == 1, the directory information for FS_FINDFIRST is a bit more complicated. An EAOP struction will be located at the beginning of pData. You should start filling in the data after the EAOP structure. The data format is:

| struct FileFromFindBuf { | | | | |
|--------------------------|-------------|---|---|---|
| long | position; | \wedge this field is not present if flags X | | |
| | | ∕\is 0. | | Х |
| unsigned short | dateCreate; | | | |
| unsigned short | timeCreate; | | | |
| unsigned short | dateAccess; | | | |
| unsigned short | timeAccess; | | | |
| unsigned short | dateWrite; | | | |
| unsigned short | timeWrite; | | | |
| long | cbEOF; | | | |
| long | cbAlloc; | | | |
| unsigned short | attr; | | | |
| FEALIST | fealist; | ∧this is a variable length field | Х | |
| unsigned char | cbName; | | | |
| unsigned char | szName[]; | | | |
| } | | | | |

For a description of the FEALIST structure, see "FEAs" on page 1-9.

If the non-8.3 filename format bit is set in the attributes of a file found by FS_FINDFIRST/NEXT/FROMNAME, it must be turned off in the copy of the attributes returned in pData.

If FS_FINDFIRST for a particular search returns an error, an FS_FINDCLOSE for that search will not be issued.

Sufficient information to find the next matching directory entry must be saved in the fsfsd data structure.

In the case where directory entry information overflows the pData area, the FSD should be able to continue the search from the entry which caused the overflow on the next FS_FINDNEXT or FS_FINDFROMNAME.

In the case of a global search in a directory, the first two entries in that directory as reported by the FSD should be '.' and '..' (current and the parent directories).

Note: The FSD will be called with the FINDFIRST/FINDFROMNAME interface when the 32-bit DosFindFirst/DosFindNext APIs are called. THIS IS A CHANGE FROM 1.X IFS interface for redirector FSDs. The kernel will also be massaging the find records so that they appear the way the caller expects. Redirectors who have to resume searches should take this information into account. (i.e. You might want to reduce the size of the buffer sent to the server, so that the position fields can be added to the beginning of all the find records).

Application Note: Some applications have been coded to expect behavior beyond the architectural requirements. For example, there are applications that require DosFindFirst to return an entry for a file that has been open-created, but which has never been closed. You can debate whether a file truly exists until it has been closed, but unless the applications are changed they will still not work. Consequently, it is recommended that FSDs exhibit this behavior.

FS FINDFROMNAME Find matching file name(s) starting from name

Purpose

Find occurrence(s) of file name(s) in a directory starting from a position or name.

Calling Sequence

int far pascal FS_FINDFROMNAME (psfsfsi, pfsfsd, pData, cbData, pcMatch,

struct fsfsi far \ pfsfsi; pData; cbData; level; position; pName; flags;

level, position, pName, flags)

struct fsfsd far \setminus pfsfsd; char far \ unsigned short unsigned short far \pcMatch; unsigned short unsigned long char far \setminus unsigned short

Where

pfsfsi

is a pointer to the file-system-independent file search structure. The FSD should not update this structure.

pfsfsd

is a pointer to the file-system-dependent file search structure. The FSD may use this to store information about continuation of the search.

pData

is the address of the application data area.

Addressing of this data area has not been validated by the kernel (see FSH_PROBEBUF). The FSD will fill in this area with a set of packed, variablelength structures that contain the requested data and matching file names in the format required for DosFindFirst/Next.

cbData

is the length of the application data area in bytes.

pcMatch

is a pointer to the number of matching entries. The FSD will return at most this number of entries. The FSD will store into it the number of entries actually placed in the data area. The FSD does not need to validate this pointer.

level

is the information level to be returned. Level selects among a series of structures of data to be returned. The level passed to the FSD is valid.

position

is the file-system-specific information about where to restart the search from. This information was returned by the FSD in the ResultBuf for a DosFindFirst2/Next/FromName call.

pName

is the filename from which to continue the search. The FSD does not need to validate this pointer.

flags

indicates whether to return file position information. The flag passed to the FSD has a valid value.

- flags == FF_NOPOS (0x00) indicates that file-position information should not be returned, see FS_FINDFIRST.
- flags == FF_GETPOS (0x01) indicates that file-position information should be returned in the information format described under FS_FINDFIRST.

Remarks

The FSD may use the position or filename or both to determine the position from which to resume the directory search. Support of this entry point requires the ability to "resynch" or "rewind" a search request. The operating system can request that you start the search over with the file following the filename in pName. The information in **position** is the value that the FSD put in the position field in that file's FILEFINDBUF structure in a previous search request.

For flags == 1, the FSD must store in the position field adequate information to allow the search to be resumed from the file by calling FS_FINDFROMNAME. See FS_FINDFIRST for a description of the data format.

The FSD must ensure that enough information is stored in the fsfsd data structure to enable it to continue the search.

Note: The FSD will be called with the FINDFIRST/FINDFROMNAME interface when the 32-bit DosFindFirst/DosFindNext APIs are called. THIS IS A CHANGE FROM 1.X IFS interface for redirector FSDs. The kernel will also be massaging the find records so that they appear the way the caller expects. Redirectors who have to resume searches should take this information into account. (i.e. You might want to reduce the size of the buffer sent to the server, so that the position fields can be added to the beginning of all the find records).

FS_FINDNEXT Find next matching file name.

Purpose

Find the next occurrence of a file name in a directory.

Calling Sequence

int far pascal FS_FINDNEXT (pfsfsi, pfsfsd, pData, cbData, pcMatch, level, flags)

| struct fsfsi far \ | pfsfsi; |
|------------------------|----------|
| struct fsfsd far $\$ | pfsfsd; |
| char far \setminus | pData; |
| unsigned short | cbData; |
| unsigned short far $\$ | pcMatch; |
| unsigned short | level; |
| unsigned short | flags; |

Where

pfsfsi

is a pointer to the file-system-independent file-search structure. The FSD should not update this structure.

pfsfsd

is a pointer to the file-system-dependent file-search structure. The FSD may use this to store information about continuation of the search.

pData

is the address of the application area.

Addressing of this data area is not validated by the kernel (see FSH_PROBEBUF). The FSD fills in this area with a set of packed, variable-length structures that contain the requested data and matching file names.

cbData

is the length of the application data area in bytes.

pcMatch

is a pointer to the number of matching entries.

The FSD returns, at most, this number of entries. The FSD returns the the number of entries actually placed in the data area in this parameter.

The FSD does not need to validate this pointer.

level

is the information level to be returned. Level selects among a series of structures of data to be returned. The level passed to the FSD is valid.

flags

indicates whether to return file-position information.

- flags == FF_NOPOS (0x00) indicates that file-position information should not be returned, see FS_FINDFIRST.
- flags == FF_GETPOS (0x01) indicates that file-position information should be returned in the information format described under FS_FINDFIRST.

Remarks

For flags == FF_GETPOS, the FSD must store in the position field adequate information to allow the search to be resumed from the file by calling FS_FINDFROMNAME. See FS_FINDFIRST for a description of the data format.

The level passed to FS_FINDNEXT is the same level as that passed to FS_FINDFIRST to initiate the search.

Sufficient information to find the next matching directory entry must be saved in the fsfsd data structure.

The FSD should take care of the case where the pData area overflow may occur. FSDs should be able to start the search from the same entry for the next FS_FINDNEXT as the one for which the overflow occurred.

FS_FINDNOTIFYCLOSE Close Find-Notify Handle

Purpose

This function is now obsolete. The notification of file system changes is now being supported by the generic IFS mechanism. Removal of the entry point would result in unmodified FSDs being incompatible, so it was left in. Returning ERROR_NOT_SUPPORTED is recommended. The original function was to close the association between a Find-Notify handle and a DosFindNotifyFirst or DosFindNotifyNext function.

Calling Sequence

int far pascal FS_FINDNOTIFYCLOSE (handle)

unsigned short handle;

Where

handle

is the directory handle.

This handle was returned by the FSD on a previous FS_FINDNOTIFYFIRST or FS_FINDNOTIFYNEXT call.

Remarks

FS FINDNOTIFYFIRST Monitor a directory for changes.

Purpose

This function is now obsolete. The notification of file system changes is now being supported by the generic IFS mechanism. Removal of the entry point would result in unmodified FSDs being incompatible, so it was left in. Returning ERROR_NOT_SUPPORTED is recommended. The original function was to start monitoring a directory for changes.

Calling Sequence

int far pascal FS_FINDNOTIFYFIRST (pcdfsi, pcdfsd, pName, iCurDirEnd, attr, pHandle, pData, cbData, pcMatch, level, timeout)

struct cdfsi far \ pcdfsi; struct cdfsd far \ char far \ unsigned short iCurDirEnd; unsigned short attr: unsigned short far \ pHandle; char far \ unsigned short unsigned short far \setminus pMatch; unsigned short unsigned long

pcdfsd; pName; pData; cbData; level: timeout;

Where

pcdfsi

is a pointer to the file-system-independent working directory structure.

pcdfsd

is a pointer to the file-system-dependent working directory structure.

pName

is a pointer to the ASCIIZ name of the file or directory.

Wildcard characters are allowed only in the last component. The FSD does not need to verify this pointer.

iCurDirEnd

is the index of the end of the current directory in pName.

This is used to optimize FSD path processing. If iCurDirEnd == -1 there is no current directory relevant to the name text, that is, a device.

attr

is the bit field that governs the match.

Any directory entry whose attribute bit mask is a subset of attr and whose name matches that in pName should be returned. See FS_FINDFIRST for an explanation.

pHandle

is a pointer to the handle for the find-notify request.

The FSD allocates a handle for the find-notify request, that is, a handle to the directory monitoring continuation information, and stores it here. This handle is passed to FS_FINDNOTIFYNEXT to continue directory monitoring.

The FSD does not need to verify this pointer.

pData

is the address of the application data area.

Addressing of this data area is not validated by the kernel (see FSH&PROBEBUF). The FSD fills in this area with a set of packed, variable-length structures that contain the requested data and matching file names.

cbData

is the length of the application data area in bytes.

pcMatch

is a pointer to the number of matching entries.

The FSD returns, at most, this number of entries. The FSD returns in this parameter the number of entries actually placed in the data area.

The FSD does not need to verify this pointer.

level

is the information level to be returned.

Level selects among a series of data structures to be returned. See the description of DosFindNotifyFirst in the *OS/2 Version 3.0 Control Program Programming Reference* for more information.

The level passed to the FSD is valid.

timeout

is the timeout in milliseconds.

The FSD waits until either the timeout has expired, the buffer is full, or the specified number of entries has been returned before returning to the caller.

Remarks

None.

FS_FINDNOTIFYNEXT Resume reporting directory changes

Purpose

This function is now obsolete. The notification of file system changes is now being supported by the generic IFS mechanism. Removal of the entry point would result in unmodified FSDs being incompatible, so it was left in. Returning ERROR_NOT_SUPPORTED is recommended. The original function was to resume reporting of changes to a file or directory.

Calling Sequence

int far pascal FS_FINDNOTIFYNEXT (handle, pData, cbData, pcMatch, level, timeout)

 unsigned short
 handi

 char far \
 pData

 unsigned short
 cbDa

 unsigned short far \
 pcMatch;

 unsigned short
 leve

 unsigned long
 timeo

handle; pData; cbData; /atch; level; timeout:

Where

handle

is the handle to the find-notify request.

This handle was returned by the FSD and is associated with a previous FS_FINDNOTIFYFIRST or FS_FINDNOTIFYNEXT call.

pData

is the address of the application data area.

Addressing of this data area is not validated by the kernel (see FSH_PROBEBUF). The FSD fills in this area with a set of packed, variable-length structures that contain the requested data and matching file names.

cbData

is the length of the application data area in bytes.

pcMatch

is a pointer to the number of matching entries.

The FSD returns, at most, this number of entries. The FSD returns in this parameter the number of entries actually placed in the data area.

The FSD does not need to verify this pointer.

level

is the information level to be returned.

Level selects among a series of data structures to be returned. See the description of DosFindNotifyFirst in the *OS/2 Version 3.0 Control Program Programming Reference* for more information.

The level passed to the FSD is valid.

timeout

is the timeout in milliseconds.

The FSD waits until either the timeout has expired, the buffer is full, or the specified number of entries has been returned before returning to the caller.

Remarks

pcMatch is the number of changes required to directories or files that match the pName target and attr specified during a related, previous FS_FINDNOTIFYFIRST. The file system uses this field to return the number of changes that actually occurred since the issue of the present FS_FINDNOTIFYNEXT.

The level passed to FS_FINDNOTIFYNEXT is the same level as that passed to FS_FINDNOTIFYFIRST to initiate the search.

FS_FLUSHBUF Commit file buffers

Purpose

Flushes cache buffers for a specific volume.

Calling Sequence

int far pascal FS_FLUSHBUF (hVPB, flag)

unsigned short unsigned short hVPB; flag;

Where

hVPB

is the handle to the volume for flush.

flag

is used to indicate discarding of cached data.

flag == FLUSH_RETAIN (0x00) indicates cached data may be retained. flag == FLUSH_DISCARD (0x01) indicates the FSD will discard any cached data after flushing it to the specified volume.

All other values are reserved.

Remarks

After this call is completed, the volume should be in a consistent state. In other words, if the media went off line, CHKDSK should not find any discrepancy in your file system structure if the media was then mounted at a later date. "Dirty" flags may still be set, but the file system structures should be committed.

FS_FSCTL File System Control

Purpose

Allow an extended standard interface between an application and a file system driver.

This is the official, architected way to implement any functions that are unique to your file system. The FS_IOCTL is intended for functions that will be primarily serviced by the device driver.

Calling Sequence

int far pascal FS_FSCTL (pArgdat, iArgType, func, pParm, lenParm, plenParmIO, pData, lenData, plenDataIO)

union argdat far \ pArgDat; unsigned short iArgType; unsigned short func; char far $\$ pParm; lenParm; unsigned short unsigned short far \ plenParmIO; char far \setminus pData; unsigned short lenData; unsigned short far \ plenDataIO;

Where

pArgDat

is a pointer to the union whose contents depend on iArgType. The union is defined as follows:

union argdat {

```
\wedgepArgType = 1, FileHandle directed case \vee
struct sf {
         struct sffsi far \psfsi;
         struct sffsd far \psfsd;
};
\wedgepArgType = 2, Pathname directed case X
struct cd {
         struct cdfsi far \pcdfsi;
         struct cdfsd far \pcdfsd;
         char far \
                               pPath;
         unsigned short iCurDirEnd;
};
∧pArgType = 3, FSD Name directed case
                                               χ
                                                  χ
/pArgDat is Null
```

}; iArgType

indicates the argument type.

iArgType = FSCTL_ARG_FILEINSTANCE (0x01)

means that pArgDat->sf.psfsi and pArgDat->sf.psfsd point to an sffsi and sffsd, respectively.

iArgType = FSCTL_ARG_CURDIR (0x02)

means that pArgDat->cd.pcdfsi and pArgDat->cd.pcdfsd point to a cdfsi and cdfsd, pArgDat->cd.pPath points to a canonical pathname, and pArgDat->cd.iCurDirEnd gives the index of the end of the current directory in pPath. The FSD does not need to verify the pPath pointer. iArgType = FSCTL_ARG_NULL (0x03)

means that the call was FSD name routed, and pArgDat is a NULL pointer.

func

indicates the function to perform.

func == FSCTL_FUNC_NEW_INFO (0x01) indicates a request for new error code information.

func == FSCTL_FUNC_EASIZE (0x02) indicates a request for the maximum EA size and EA list size supported by the FSD.

pParm

is the address of the application input parameter area.

Addressing of this data area has not been validated by the kernel (see FSH_PROBEBUF).

lenParm

is the maximum length of the application parameter area (pParm).

plenParmIO

On input, contains the length in bytes of the parameters being passed in to the FSD in pParm. On return, contains the length in bytes of data returned in pParm by the FSD. The length of the data returned by the FSD in pParm must not exceed the length in lenParm. Addressing of this area is not validated by the kernel (see FSH_PROBEBUF).

pData

is the address of the application output data area.

Addressing of this data area is not validated by the kernel (see FSH_PROBEBUF).

lenData

is the maximum length of the application output data area (pData).

plenDatalO

On input, contains the length in bytes of the data being passed in to the FSD in pData. On return, contains the length in bytes of data returned in pData by the FSD. The length of the data returned by the FSD in pData must not exceed the length in lenData. Addressing of this area is not validated by the kernel (see FSH_PROBEBUF).

Remarks

The accessibility of the parameter and data buffers has not been validated by the kernel. FS_PROBEBUF must be used.

All FSDs must support func == 1 to return new error code information and func == 2 to return the limits of the EA sizes.

For func == 1, the error code is passed to the FSD in the first WORD of the parameter area. On return, the first word of the data area contains the length of the asciiz string containing an explanation of the error code. The data area con-

tains the asciiz string beginning at the second WORD. Unfortunately, no current system code or utilities use this function. Consequently, it is recommended that FSDs try to restrict themselves to the standard return code set. In the future we may be able to use this as intended.

For func == 2, the maximum EA and EA list sizes supported by the FSD are returned in the buffer pointed to by pData in the following format:

EASizeBufStruc { unsigned short easb_MaxEASize; unsigned long easb_MaxEAListSize; } Max size of an individual EA X unsigned long easb_MaxEAListSize; }

FS_FSINFO File System Information

Purpose

Returns or sets information for a file system device.

Calling Sequence

int far pascal FS_FSINFO (flag, hVPB, pData, cbData, level)

unsigned short unsigned short char far \ unsigned short unsigned short flag; hVPB; pData; cbData; level;

Where

flag

indicates retrieval or setting of information.

flag == INFO_RETRIEVE (0x00) indicates retrieving information. flag == INFO_SET (0x01) indicates setting information on the media. All other values are reserved.

hVPB

is the handle to the volume of interest.

pData

is the address of the application output data area.

Addressing of this data area has not been validated by the kernel (see (FSH_PROBEBUF).

cbData

is the length of the application data area.

For flag == 0, this is the length of the data the application wishes to retrieve. If there is not enough room for the entire level of data to be returned, the FSD will return a BUFFER OVERFLOW error. For flag == 1, this is the length of the data to be sent to the file system.

level

is the information level to be returned.

Level selects among a series of structures of data to be returned or set. See DosQFSInfo and DosSetFSInfo for information.

Remarks

None.

FS_INIT File system driver initialization

Purpose

Request file system driver initialization.

Calling Sequence

int far pascal FS_INIT (szParm, DevHelp, pMiniFSD)

char far \ szParm; unsigned long DevHelp; unsigned long far \ pMiniFSD;

Where

szParm

is a pointer to the ASCIIZ parameters following the CONFIG.SYS IFS= command that loaded the FSD. If there are no parameters, this pointer will be NULL. The FSD does not need to verify this pointer.

DevHelp

is the address of the kernel entry point for the DevHelp routines.

This is used exactly as the device driver DevHelp address, and can be used by an FSD that needs access to some of the device helper services.

pMiniFSD

is a pointer to data passed between the mini-FSD and the FSD, or null.

Remarks

This call is made during system initialization to allow the FSD to perform actions necessary for beignning operation. The FSD may successfully initialize by returning a return code of NO_ERROR or may reject installation (invalid parameters, incompatible hardware, etc.) by returning the appropriate error code. If rejection is selected, all FSD selectors and segments are released.

pMiniFSD will be null, except when booting from a volume managed by an FSD and the exported name of the FSD matches the exported name of the mini-FSD. In this case, pMiniFSD will point to data established by the mini-FSD (See mFS_INIT).

FS_IOCTL I/O Control for Devices

Purpose

Perform control function on the device specified by the opened device handle.

Calling Sequence

int far pascal FS_IOCTL (psffsi, psffsd, cat, func, pParm, lenMaxParm, plenInOutParm,

pData, lenMaxData, plenInOutData)

struct sffsi far \psffsi;struct sffsd far \psffsd;unsigned shortcat;unsigned shortfunc;char far \pParm;unsigned shortlenMaxParm;unsigned short \plenInOutParm;char far \pData;unsigned shortlenMaxData;unsigned short \plenInOutData;

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

cat

is the category of the function to be performed.

func

is the function within the category to be performed.

pParm

is the address of the application input parameter area.

Addressing of this data area is not validated by the kernel (see FSH_PROBEBUF). A null value indicates that the parameter is unspecified for this function.

lenMaxParm

is the byte length of the application input parameter area.

If lenMaxParm is 0, *plenInOutParm is 0, and pParm is not null, it means that the data buffer length is unknown due to the request being submitted via an old IOCTL or DosDevIOCtl interface.

plenInOutParm

is the pointer to an unsigned short that contains the length of the parameter area in use on input and is set by the FSD to be the length of the parameter area in use on output.

Addressing of this data area is not validated by the kernel (see FSH_PROBEBUF). A null value indicates that the parameter is unspecified for this function.

pData

is the address of the application output data area.

Addressing of this data area has not been validated by the kernel (see FSH_PROBEBUF). A null value indicates that the parameter is unspecified for this function.

lenMaxData

is the byte length of the application output data area.

If lenMaxData is 0, *plenInOutData is 0, and pData is not null, it means that the data buffer length is unknown due to the request being submitted via an old IOCTL or DosDevIOCtl interface.

plenInOutData

is the pointer to an unsigned short that contains the length of the data area in use on input and is set by the FSD to be the length of the data area in use on output.

Addressing of this data area is not validated by the kernel (see FSH_PROBEBUF). A null value indicates that the parameter is unspecified for this function.

Remarks

Note: This entry point's parameter list definition has changed from the 1.x IFS document. If the parameters plenInOutParm and plenInOutData are null, use the lenMax parameters as the buffer sizes sent to any file system helper.

FS MKDIR Make Subdirectory

Purpose

Create the specified directory.

Calling Sequence

int far pascal FS_MKDIR (pcdfsi, pcdfsd, pName, iCurDirEnd, pEABuf, flags)

struct cdfsi far \ char far \ char far \ pName; unsigned short iCurDirEnd; char far \setminus unsighed short

pcdfsi; pName; pEABuf; flags;

Where

pcdfsi

is a pointer to the file-system-independent working directory structure.

pcdfsd

is a pointer to the file-system-dependent working directory structure.

pName

is a pointer to the ASCIIZ name of the directory to be created.

The FSD does not need to verify this pointer.

iCurDirEnd

is the index of the end of the current directory in pName.

This is used to optimize FSD path processing. If iCurDirEnd == -1, there is no current directory relevant to the name text, that is, a device.

pEABuf

is a pointer to the extended attribute buffer.

This buffer contains attributes that will be set upon creation of the new directory. If NULL, no extended attributes are to be set. Addressing of this data area has not been validated by the kernel (see FSH_PROBEBUF).

flags

indicates the name type.

Flags == 0x0040 indicates a non-8.3 filename format. All other values are reserved.

Remarks

The FSD needs to do the time stamping itself. There is no aid in the kernel for time stamping sub-directories. FAT only supports creation time stamp and sets the other two fields to zeroes. An FSD should do the same. The FSD can obtain the current time/date from the infoseg.

A new directory called pName should be created if possible. The standard directory entries '.' and '..' should be put into the directory.

The non-8.3 filename format attribute in the directory entry should be set according to the value in flags.

FS_MOUNT Mount/unmount volumes

Purpose

Examination of a volume by an FSD to see if it recognizes the file system format.

Calling Sequence

int far pascal FS_MOUNT (flag, pvpfsi, pvpfsd, hVPB, pBoot)

unsigned short flag; struct vpfsi far \ pvpfsi; struct vpfsd far \ pvpfsd; unsigned short hVPB; char far \ pBoot;

Where

flag

indicates operation requested.

flag == MOUNT_MOUNT (0x00) indicates that the FSD is requested to mount or accept a volume.

flag == MOUNT_VOL_REMOVED (0x01) indicates that the FSD is being advised that the specified volume has been removed.

flag == MOUNT_RELEASE (0x02) indicates that the FSD is requested to release all internal storage assigned to that volume as it has been removed from its driver and the last kernel-managed reference to that volume has been removed.

flag == MOUNT_ACCEPT (0x03) indicates that the FSD is requested to accept the volume regardless of recognition in preparation for formatting for use with the FSD.

All other values are reserved.

The value passed to the FSD will be valid.

pvpfsi

is a pointer to the file-system-independent portion of VPB.

If the media contains an OS/2-recognizable boot sector, then the vpi_vid field contains the 32-bit identifier for that volume. If the media does not contain such a boot sector, the FSD must generate a unique label for the media and place it into the vpi_vid field.

pvpfsd

is a pointer to the file-system-dependent portion of VPB.

The FSD may store information as necessary into this area.

hVPB

is the handle to the volume

pBoot

is a pointer to sector 0 read from the media.

This pointer is only valid when flag == 0. The buffer the pointer refers to must not be modified. The pointer is always valid and does not need to be verified when flag == 0. If a read error occurred, the buffer will contain zeroes.

Remarks

The FSD examines the volume presented and determine whether it recognizes the file system. If it does, it returns zero, after having filled in appropriate parts of the vpfsi and vpfsd data structures. The vpi_vid and vpi_text fields must be filled in by the FSD. If the FSD has an OS/2 format boot sector, it must convert the label from the media into ASCIIZ form. The vpi_hDev field is filled in by OS/2. If the volume is unrecognized, the driver returns non-zero.

The vpi_text and vpi_vid must be updated by the FSD each time these values change.

The contents of the vpfsd data structure are as follows:

- FLAG = 0 The FSD is expected to issue an FSD_FINDDUPHVPB to see if a duplicate VPB exists. If one does exist, the VPB fs dependent area of the new VPB is invalid and the new VPB will be unmounted after the FSD returns from the MOUNT. The FSD is expected to update the FS dependent area of the old duplicate VPB. If no duplicate VPB exists, the FSD should initialize the FS dependent area.
- FLAG = 1 VPB FS dependent part is same as when FSD last modified it.
- FLAG = 2 VPB FS dependent part is same as when FSD last modified it.

After media recognition time, the volume parameters may be examined using the FSH_GETVOLPARM call. The volume parameters should not be changed after media recognition time.

During a mount request, the FSD may examine other sectors on the media by using FSH_DOVOLIO to perform the I/O. If an uncertain-media return is detected, the FSD is expected to clean up and return an UNCERTAIN MEDIA error in order to allow the volume mount logic to restart on the newly-inserted media. The FSD must provide the buffer to use for additional I/O.

The OS/2 kernel manages the VPB through a reference count. All volume-specific objects are labelled with the appropriate volume handle and represent references to the VPB. When all kernel references to a volume disappear, FS_MOUNT is called with flag == 2, indicating a dismount request.

When the kernel detects that a volume has been removed from its driver, but there are still outstanding references to the volume, FS_MOUNT is called with flag == 1 to allow the FSD to drop clean (or other regenerable) data for the volume. Data which is dirty and cannot be regenerated should be kept so that it may be written to the volume when it is remounted in the drive.

When a volume is to be formatted for use with an FSD, the kernel calls the FSD's FS_MOUNT entry point with flag == 3 to allow the FSD to prepare for the format operation. The FSD should accept the volume even if it is not a volume of the type that FSD recognizes, since the point of format is to change the file system on the volume. The operation may fail if formatting does not make sense. (For example, an FSD which supports only CD-ROM.)

Since the hardware does not allow for kernel-mediated removal of media, it is probable that the unmount request will be issued when the volume is not present in any drive.

FS_MOVE Move a file or subdirectory

Purpose

Moves (renames) the specified file or subdirectory.

Calling Sequence

int far pascal FS_MOVE (pcdfsi, pcdfsd,

pSrc, iSrcCurDirEnd, pDst, iDstCurDirEnd, flags)

struct cdfsi far \pcdfsi;struct cdfsd far \pcdfsd;char far \pSrc;unsigned shortiSrcCurDirEnd;char far \pDst;unsigned shortiDstCurDirEnd;unsigned shortflags;

Where

pcsfsi

is a pointer to the file-system-independent working directory structure.

pcdfsd

is a pointer to the file-system-dependent working directory structure.

pSrc

is a pointer to the ASCIIZ name of the source file or directory.

The FSD does not need to verify this pointer.

iSrcCurDirEnd

is the index of the end of the current directory in pSrc.

This is used to optimize FSD path processing. If iSrcCurDirEnd == -1 there is no current directory relevant to the source name text.

pDst

is a pointer to the ASCIIZ name of the destination file or directory.

The FSD does not need to verify this pointer.

iDstCurDirEnd

is the index of the end of the current directory in pDst.

This is used to optimize FSD path processing. If iDstCurDirEnd == -1 there is no current directory relevant to the destination name text.

flags

indicates destination name type.

Flags == 0x0040 indicates non-8.3 filename format. All other values are reserved.

Remarks

The file specified in filename should be moved to or renamed as the destination filename, if possible.

Neither the source nor the destination filename may contain wildcard characters.

FS_MOVE may be used to change the case in filenames.

The non-8.3 filename format attribute in the directory entry for the destination name should be set according to the value in flags.

In the case of a subdirectory move, the system does the following checking:

No files in this directory or its subdirectories are open.

This directory or any of its subdirectories is not the current directory for any process in the system.

In addition, the system also checks for circularity in source and target directory names; that is, the source directory is not a prefix of the target directory.

Note: OS/2 does not validate input parameters. Therefore, an FSD should call FSH_PROBEBUF where appropriate.

FS NEWSIZE Change File's Logical Size

Purpose

Changes a file's logical (EOD) size.

Calling Sequence

int far pascal FS_NEWSIZE (psffsi, psffsd, len, IOflag)

struct sffsd far \ psffsd: unsigned long unsigned short

psffsd; len: IOflag;

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

len

is the desired new length of the file.

IOflag

indicates information about the operation on the handle.

IOflag == IOFL_WRITETHRU (0x0010) indicates write-through. IOflag == IOFL_NOCACHE (0x0020) indicates no-cache.

Remarks

The FSD should return an error if an attempt is made to write beyond the end of the volume with a direct access device handle.

The file system driver attempts to set the size (EOD) of the file to newsize and update sfi_size, if successful. If the new size is larger than the currently allocated size, the file system driver arranges for for efficient access to the newly-allocated storage.

Of the information passed in IOflag, the write-through bit is a mandatory bit in that any data written to the block device must be put out on the medium before the device driver returns. The no-cache bit, on the other hand, is an advisory bit that says whether the data being transferred is worth caching or not.

It is legal for the user to attempt to read an area of a file that has been allocated but not written to. Architecturally, that area is undefined and can be whatever data is in that area. However, returning a zero-filled buffer for uninitialized file data is recommended.

FS_NMPIPE Do a remote named pipe operation.

Purpose

Perform a special purpose named pipe operation remotely.

Calling Sequence

int far pascal FS_NMPIPE (psffsi, psffsd, OpType, pOpRec, pData, pName)

| struct sffsi far \ | psffsi; |
|------------------------------|---------|
| struct sffsd far $\$ | psffsd; |
| unsigned short | OpType; |
| union npoper far \setminus | pOpRec; |
| char far \setminus | pData; |
| char far \setminus | pName; |

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

ОрТуре

is the operation to be performed. This parameter has the following values:

| NMP_GetPHandState | 0x21 |
|---------------------|------|
| NMP_SetPHandState | 0x01 |
| NMP_PipeQInfo | 0x22 |
| NMP_PeekPipe | 0x23 |
| NMP_ConnectPipe | 0x24 |
| NMP_DisconnectPipe | 0x25 |
| NMP_TransactPipe | 0x26 |
| NMP_ReadRaw | 0x11 |
| NMP_WriteRaw | 0x31 |
| NMP_WaitPipe | 0x53 |
| NMP_CallPipe | 0x54 |
| NMP_QNmPipeSemState | 0x58 |

pOpRec

is the data record which varies depending on the value of OpType. The first parameter in each structure encodes the length of the parameter block. The second parameter, if non-zero, indicates that the pData parameter is supplied and gives its length. The following record formats are used:

union npoper {

| struct | phs_param | phs; |
|--------|------------|-------|
| struct | npi_param | npi; |
| struct | npr_param | npr; |
| struct | npw_param | npw; |
| struct | npq_param | npq; |
| struct | npx_param | npx; |
| struct | npp_param | npp; |
| struct | npt_param | npt; |
| struct | qnps_param | qnps; |
| struct | npc_param | npc; |
| struct | npd_param | npd; |
| | | |

```
struct phs_param {
    short
               phs_len;
    short
              phs_dlen;
    short
            phs_pmode; \land pipe mode set or returned \land
};
∧DosQNmPipeInfo parameter block X
struct npi_param {
    short
               npi_len;
    short
              npi_dlen;
    short
            npi_level; \land information level desired X
};
∧DosRawReadNmPipe parameters X
/\data is buffer addr
                            χ
struct npr_param {
    short
              npr_len;
    short
            npr_dlen;
    short
            npr_nbyt;
                         \wedge\, number of bytes read {\tt X}
};
∧data is buffer addr
                             χ
struct npw_param {
    short
              npw_len;
            npw_dlen;
    short
                          \wedge\, number of bytes written {\tt X}
    short
            npw_nbyt;
};
∧NPipeWait parameters X
struct npq_param {
    short
               npq_len;
    short
              npq_dlen;
                            ∧timeout in milliseconds X
    long
              npq_timeo;
                           ∧priority of caller
    short
               npq_prio;
                                                   χ
};
∧DosCallNmPipe parameters X
∧data is in-buffer addr
                       Х
struct npx_param {
    short
                       npx_len;
                                 \wedge length of in-buffer
    unsigned short
                    npx_ilen;
                                                           χ
                                 ∧pointer to out-buffer
                                                         χ
    char far \setminus
                    npx_obuf;
                                 \wedge length of out-buffer
                                                           χ
    unsigned short
                    npx_ilen;
    unsigned short
                     npx_nbyt; \lambda number of bytes read
                      npx_timeo; ∧timeout in milliseconds X
    long
};
```

 \land PeekPipe parameters, data is buffer addr \land

χ

struct npp_param {

```
short
                         npp_len;
    unsigned short
                       npp_dlen;
                                                                     χ
    unsigned short
                       npp_nbyt;
                                    \wedge number of bytes read
     unsigned short
                       npp_av10;
                                     \wedge bytes left in pipe
                                                                    χ
     unsigned short
                       npp_av11;
                                     \wedge bytes left in current msg X
     unsigned short npp_state;
                                    ∧pipe state
                                                                   χ
};
∧DosTransactNmPipe parameters X
∧data is in-buffer addr
                               χ
struct npt_param {
    short
                         npt_len;
    unsigned short
                      npt_ilen;
                                   \wedge length of in-buffer X
     char far \
                      npt_obuf;
                                   ∧pointer to out-buffer X
     unsigned short
                       npt_olen;
                                   \wedge length of out-buffer \times
     unsigned short
                       npt_nbyt;
                                   \wedge number of bytes read \vee
};
∧QNmPipeSemState parameter block X
∧data is user data buffer
                                  χ
struct qnps_param {
                       qnps_len; \land length of parameter block
                                                                         χ
     unsigned short
                                    \land length of supplied data block X
     unsigned short
                      qnps_dlen;
     long
                        qnps_semh;
                                        \wedge system semaphore handle
                                                                         χ
     unsigned short
                     qnps_nbyt;
                                    \wedge number of bytes returned
};
∧ConnectPipe parameter block, no data block X
struct npc_param {
                                     \land length of parameter block \land
     unsigned short
                        npc_len;
     unsigned short
                       npc_dlen;
                                   \wedge length of data block
                                                                   χ
};
∧DisconnectPipe parameter block, no data block X
struct npd_param {
     unsigned short
                       npd_len;
                                     \land length of parameter block X
     unsigned short npd_dlen;
                                     /\length of data block
                                                                  χ
};
```

pData

is a pointer to a user data for operations which require it. When the pointer is supplied, its length will be given by the second element of the pOpRec structure.

pName

is a pointer to a remote pipe name. Supplied only for NMP_WAITPIPE and NMP_CALLPIPE operations. For these two operations only, the psffsi and psffsd parameters have no significance.

X

Remarks

This entry point is for support of special remote named pipe operations. Not all pointer parameters are used for all operations. In cases where a particular pointer has no significance, it will be NULL.

This entry point will be called only for the UNC FSD. Non-UNC FSDs are required to have this entry point, but should return NOT SUPPORTED if called.

FS_OPENCREATE Open a file

Purpose

Opens (or creates) the specified file.

Calling Sequence

int far pascal FS_OPENCREATE (pcdfsi, pcdfsd, pName, iCurDirEnd,

psffsi, psffsd, ulOpenMode, usOpenFlag, pusAction, usAttr, pcEABuf, pfgenflag)

| struct cdfsi far \ | pcdfsi; |
|------------------------|-------------|
| struct cdfsd far \ | pcdfsd; |
| char far \setminus | pName; |
| unsigned short | iCurDirEnd; |
| struct sffsi far $\$ | psffsi; |
| struct sffsd far $\$ | psffsd; |
| unsigned long | ulOpenMode; |
| unsigned short | usOpenFlag; |
| unsigned short far $\$ | pusAction; |
| unsigned short | usAttr; |
| char far \setminus | pcEABuf; |
| unsigned short far $\$ | pfgenflag; |

Where

pcdfsi

is a pointer to the file-system-independent working directory structure.

The contents of this structure are invalid for direct access opens.

pcdfsd

is a pointer to the file-system-dependent working directory structure. The contents of this structure are invalid for direct access opens. For remote character devices, this field contains a pointer to a DWORD that was obtained from the remote FSD when the remote device was attached to this FSD. The FSD can use this DWORD to identify the remote device.

pName

is a pointer to the ASCIIZ name of the file to be opened.

The FSD does not need to verify this pointer.

iCurDirEnd

is the index of the end of the current directory in pName.

This is used to optimize FSD path processing. If iCurDirEnd == -1, there is no current directory relevant to the name text, that is a device. This value is invalid for direct access opens.

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

ulOpenMode

indicates the desired sharing mode and access mode for the file handle.

See *OS/2 Version 3.0 Control Program Programming Reference* for a description of the OpenMode parameter for DosOpen.

An additional access mode 3 is defined when the file is being opened on behalf of OS/2, loaded for purposes of executing a file or loading a module. If the file system does not support an executable attribute, it should treat this access mode as open for reading. The value of ulOpenMode passed to the FSD will be valid.

usOpenFlag

indicates the action taken when the file is present or absent.

See *OS/2 Version 3.0 Control Program Programming Reference* for a description of the usOpenFlag parameter for DosOpen.

The value of openflag passed to the FSD is valid. This value is invalid for direct access opens.

pusAction

is the location where the FSD returns a description of the action taken as governed by openflag.

The FSD does not need to verify this pointer. The contents of Action are invalid on return for direct access opends.

usAttr

are the OS/2 file attributes.

This value is invalid for direct access opens.

pcEABuf

is a pointer to the extended attribute buffer.

This buffer contains attributes that will be set upon creation of a new file or upon replacement of an existing file. If NULL, no extended attributes are to be set. Addressing of this data area has not been validated by the OS/2 kernel (see FSH_PROBEBUF). The contents of EABuf are invalid on return for direct access opens.

pfgenflag

is a pointer to an unsigned short of flags returned by the FSD. The only flag currently defined is 0x0001 fGenNeedEA, which indicates that there are critical EAs associated with the file. The FSD does not need to verify this pointer.

Remarks

For the file create operation, if successful, ST_CREAT and ST_PCREAT are set. This causes the file to have zero as last read and last write time. If the last read/write time stamps are to be the same as the create time, simply set ST_SWRITE, ST_PWRITE, ST_SREAD, and ST_PREAD as well.

For the file open operation, the FSD copies all supported time stamps from the directory entry into the SFT.

Note: ALSO NEW FOR 2.0, it is suggested that the FSD copy the DOS file attributes from the directory entry into the SFT. This allows the FSD and the OS2 kernel to handle FCB opens more efficiently.

The sharing mode may be zero if this is a request to open a file from the DOS mode or for an FCB request.

FCB requests for read-write access to a read-only file are mapped to read-only access and reflected in the sfi_mode field by the FSD. An FCB request is indicated by the third bit set in the sfi_type field.

The flags defined for the sfi_type field are:

type == 0x0000 indicates file. type == 0x0001 indicates device. type == 0x0002 indicates named pipe. type == 0x0004 indicates FCB open. All other values are reserved.

FSDs are required to initialize the sfi_type field, preserving the FCB bit.

On entry, the sfi_hvpb field is filled in. If the file's logical size (EOD) is specified, it is passed in the sfi_size field. To the extent possible, the file system tries to allocate this much storage for efficient access.

Extended attributes are set for:

- 1. the creation of a new file
- 2. the truncation of an existing file
- 3. the replacement of an existing file.

They are not set for a normal open of an existing file.

If the standard OS/2 file creation attributes are specified, they are passed in the attr field. To the extent possible, the file system interprets the extended attributes and applies them to the newly-created or existing file. Extended attributes (EAs) that the file system does not itself use are retained with the file and not discarded or rejected.

When replacing an existing file, the FSD should not change the case of the existing file.

FSDs are required to support direct access opens. These are indicated by a bit set in the sffsi.sfi_mode field. See *OS/2 Version 3.0 Control Program Programming Reference* for more information on DosOpen. Some of the parameters passed to the FSD for direct access opens are invalid, as described above.

On a successful return, the following fields in the sffsi structure must be filled in by the file system driver: sfi_size and all the time and date fields.

The file-system-dependent portion of an open file instance passed to the FSD for FS_OPENCREATE is never initialized.

Infinite FCB opens of the same file by the same DOS mode process is supported. The first open is passed through to the FSD. Subsequent opens are not seen by the FSD.

Any non-zero value returned by the FSD indicates that the open failed and the file is not open.

Note: This entry point's parameter list definition has changed from the 1.x IFS document. The OpenMode parameter has been widened from a unsigned short to a unsigned long. The upper word of the long is relevant only to a special SPOOLER FSD. For information about the upper word please contact the OS/2 Techinal Interface group for the OEMI document for the 2.0 API

FS_OPENPAGEFILE Create paging file and handle

Purpose

Creates/opens the paging file for the Pager.

Calling Sequence

int far pascal FS_OPENPAGEFILE (pFlags, pcMaxReq, pName, psffsi, psffsd, usOpenMode, usOpenFlag, usAttr, Reserved)

unsigned long far \pFlag;unsigned long far \pcMaxReq;char far \pName;struct sffsi far \psffsi;unsigned shortusOpenMode;unsigned shortusOpenFlag;unsigned shortusAttr;unsigned longReserved;

Where

pFlag

is a pointer to a flag double word for passing of information between the pager and the file system.

pFlag == PGIO_FIRSTOPEN (0x00000001) indicates first open of the page file.

pFlag == PGIO_PADDR (0x00004000) indicates physical addresses are required in the page list.

pFlag == PGIO_VADDR (0x00008000) indicates 16:16 virtual addresses are required in the page list.

All other values are reserved.

pcMaxReq

is a pointer to a unsigned long where the FSD places the maximum request list length that can be managed by Enchanced strategy device driver.

pName

is a pointer to the ASCIIZ path and filename of the paging file.

psffsi

is a pointer to the file-system-independent portion of an open file instance.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

usOpenMode

indicates the desired sharing mode and access mode for the file handle.

See *OS/2 Version 3.0 Control Program Programming Reference* for a description of the OpenMode parameter for DosOpen.

usOpenFlag

indicates the action taken when the file is present or absent.

See *OS/2 Version 3.0 Control Program Programming Reference* for a description of the usOpenFlag parameter for DosOpen.

usAttr

are the OS/2 file attributes.

Reserved

is a double word parameter reserved for use in the future.

Remarks

Enough information is provided for the FSD to perform a "normal" open/create call.

Since a page file has special requirements about contiguity of its allocations, FS_OpenPageFile must assure that any data sectors allocated are returned (Create call only). FS_AllocatePageSpace will be called to handle file allocation.

If the FSD cannot support the FS_DoPageIO (usually due to an disk device driver which does not support the Extended strategy entry point), the FSD can return zero (0) for *pcMaxReq. This tells the kernel file system that it must emulate FS_DoPageIO.

The FSD can require either physical or virtual (16:16) addresses for subsequent calls to FS_DoPageIO. This allows an FSD to emulate FS_DoPageIO without having to worry about dealing with physical addresses.

For a detailed description of the Extended Strategy request interface please see the *OS/2 Version 3.0 Physical Device Driver Reference*.

FS_PATHINFO Query/Set a File's Information

Purpose

Returns information for a specific path or file.

Calling Sequence

int far pascal FS_PATHINFO (flag, pcdfsi, pcdfsd, pName, iCurDirEnd, level, pData, cbData)

| unsigned short | flag; |
|----------------------|-------------|
| struct cdfsi far \ | pcdfsi; |
| struct cdfsd far $\$ | pcdfsd; |
| char far $\$ | pName; |
| unsigned short | iCurDirEnd; |
| unsigned short | level; |
| char far $\$ | pData; |
| unsigned short | cbData; |
| | |

Where

flag

indicates retrieval or setting of information.

flag == $PI_RETRIEVE$ (0x0000) indicates retrieving information flag == PI_SET (0x0001) indicates setting information on the media flag == 0x0010 indicates that the information being set must be writtenthrough onto the disk before returning. This bit is never set when retrieving information.

All other values are reserved.

pcdfsi

is a pointer the file-system-independent working directory structure.

pcdfsd

is a pointer to the file-system-dependent working directory structure.

pName

is a pointer to the ASCIIZ name of the file or directory for which information is to be retrieved or set.

The FSD does not need to verify this pointer.

iCurDirEnd

is the index of the end of the current directory in pName.

This is used to optimize FSD path processing. If iCurDirEnd == -1, there is no current directory relevant to the name text, that is a device.

level

is the information level to be returned.

Level selects among a series of data structures to be returned or set.

pData

is the address of the application data area.

Addressing of this data area is not validated by the kernel (see FSH_PROBEBUF). When retrieval (flag == 0) is specified, the FSD places the

information into the buffer. When outputting information to a file (flag == 1), the FSD retrieves that data from the application buffer.

cbData

is the length of the application data area.

For flag == 0, this is the length of the data the application wishes to retrieve. If there is not enough room for the entire level of data to be returned, the FSD returns a BUFFER OVERFLOW error. For flag == 1, this is the length of data to be applied to the file.

Remarks

See the descriptions of DosQPathInfo and DosSetPathInfo in the *OS/2 Version 3.0 Control Program Programming Reference* for details on information levels. However, since the IFS architecture is still 16 Bit, the data structures that the FSD returns are the structures GEA, GEALIST, FEA, FEALIST, and EAOP- not the GEA2, GEA2LIST, etc. OS/2 will convert the structure to the appropriate 32 Bit form for 32 Bit applications. In addition to the information levels described in the *OS/2 Version 3.0 Control Program Programming Reference* level 4 support is required in all FSDs. For level 4, ignore the GEALIST and return all EAs to the caller in the FEALIST. The external publication of level 4 for 32 bit applications is being considered at this time. This call will not be officially supported for 16 Bit applications since we are hoping in the future to permit extended attributes to exceed 64K and that would break those applications. Also see the documentation of the FS_FILEINFO for a description of the 16 bit data structures.

Note: This entry point should not modify the file size.

The FSD will not be called for DosQPathInfo level 5.

FSDs that are case-preserving(like HPFS) can decide to accept level 7 requests. A level 7 DosQueryPathInfo request asks the FSD to fill the pData buffer with the case-preserved path and filename of the path/filename passed in pName. Routing of level 7 requests will be determined by the kernel by checking the LV7 bit in a FSD's attribute double word.

FS_PROCESSNAME Allow FSD to modify name after OS/2 canonicalization

Purpose

Allow an FSD to modify filename to its own specification after the OS/2 canonicalization process has completed.

Calling Sequence

int far pascal FS_PROCESSNAME (pNameBuf)

char far \setminus

Where

pNameBuf

is a pointer to the ASCIIZ pathname.

pNameBuf;

The FSD should modify the pathname in place. The buffer is guaranteed to be the length of the maximum path. The FSD does not need to verify this pointer.

Remarks

The resulting name must be within the maximum path length returned by DosQSysInfo.

This routine allows the FSD to enforce a different naming convention than OS/2. For example, an FSD could remove blanks embedded in component names or return an error if it found such blanks. It is called after the OS/2 canonicalization process has succeeded. It is not called for FSH_CANONICALIZE.

This routine is called for all APIs that use pathnames.

This routine must return no error if the function is not supported.

This routine is heavily utilized. The FSD should try to keep its performance optimal.

FS_READ Read from a File

Purpose

Read the specified number of bytes from a file to a buffer location.

Calling Sequence

int far pascal FS_READ (psffsi, psffsd, pData, pLen, IOflag)

| struct sffsi far \ | psffsi; |
|------------------------|---------|
| struct sffsd far $\$ | psffsd; |
| char far $\$ | pData; |
| unsigned short far $\$ | pLen; |
| unsigned short | IOflag; |

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

sfi_position is the location within the file where the data is to be read from. The FSD should update the sfi_position field.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

pData

is the address of the application data area.

Addressing of this data area has not been validated by the kernel (see FSH_PROBEBUF).

pLen

is a pointer to the length of the application data area.

On input, this is the number of bytes to be read. On output, this is the number of bytes successfully read. If the application data area is smaller than the length, no transfer is to take place. The FSD will not be called for zero length reads. The FSD does not need to verify this pointer.

IOflag

indicates information about the operation on the handle.

IOflag == IOFL_WRITETHRU (0x0010) indicates write-through IOflag == IOFL_NOCACHE (0x0020) indicates no-cache

Remarks

If read is successful and is a file, the FSD should set ST_SREAD and ST_PREAD to make the kernel time stamp the last modification time in the SFT.

Of the information passed in IOflag, the write-through bit is a mandatory bit in that any data written to the block device must be put out on the medium before the device driver returns. The no-cache bit, on the other hand, is an advisory bit that says whether the data being transferred is worth caching or not.

It is legal for the user to attempt to read an area of a file that has been allocated but not written to. Architecturally, that area is undefined and can be whatever data is in that area. However, returning a zero-filled buffer for uninitialized file data is recommended.

An attempt to read past the end of file should result in a zero return code and the contents of pLen set to the number of bytes successfully read until the end of file or zero if the entire read is beyond the end of the file.

If an FSD supports file locking, it is responsible for checking if there are any locks on the file that should prevent the call from being executed. OS/2 will not do any lock checking if the FSA_LOCK bit is set in the FSD Attributes.

FS RMDIR Remove Subdirectory

Purpose

Removes a subdirectory from the specified disk.

Calling Sequence

int far pascal FS_RMDIR (pcdfsi, pcdfsd, pName, iCurDirEnd)

struct cdfsi far \ char far $\$ unsigned short iCurDirEnd;

pcdfsi; pName;

Where

pcdfsi

is a pointer to the file-system-independent working directory structure.

pcdfsd

is a pointer to the file-system-dependent working directory structure.

pName

is a pointer to the ASCIIZ name of the directory to be removed.

The FSD does not need to verify this pointer.

iCurDirEnd

is the index of the end of the current directory in pName.

This is used to optimize FSD path processing. If iCurDirEnd == -1, there is no directory relevant to the name text, that is a device.

Remarks

OS/2 assures that the directory being removed is not the current directory nor the parent of any current directory of any process.

The FSD should not remove any directory that has entries other than '.' and '..' in it.

FS_SETSWAP Notification of swap-file ownership

Purpose

Perform whatever actions are necessary to support the swapper.

Calling Sequence

int far pascal FS_SETSWAP (psffsi, psffsd)

struct sffsi far \psffsi; struct sffsd far \psffsd;

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance of the swapper file.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

Remarks

Swapping does not begin until this call returns successfully. This call is made during system initialization.

The FSD makes all segments that are relevant to swap-file I/O non-swappable (see FSH_FORCENOSWAP). This includes any data and code segments accessed during a read or write.

Any FSD that manages writeable media may be the swapper file system.

FS_SETSWAP may be called more than once for the same or different volumes or FSDs.

FS_SHUTDOWN Shutdown file system

Purpose

Used to shutdown an FSD in preparation for power-off or IPL.

Calling Sequence

int far pascal FS_SHUTDOWN (type, reserved) unsigned short type; unsigned long reserved;

Where

type

indicates what type of a shutdown operation to perform.

type == SD_BEGIN (0x00) indicates that the shutdown sequence is beginning. The kernel will not allow any new I/O calls to reach the FSD. The only exception will be I/O to the swap file by the swap thread through the FS_READ and FS_WRITE entry points. The kernel will still allow any thread to call FS_COMMIT, FS_FLUSHBUF and FS_SHUTDOWN. The FSD should complete all pending calls that might generate disk corruption.

type == SD_COMPLETE (0x01) indicates that the shutdown sequence is ending. An FS_COMMIT has been called on every SFT open on the FSD and following that an FS_FLUSHBUF on all volumes has been called. All final clean up activity must be completed before this call returns.

reserved

reserved for future expansion.

Remarks

From the perspective of an FSD, the shutdown sequence looks like this:

First, the system will call the FSD's FS_SHUTDOWN entry with type == 0. This notifies the FSD that the system will begin committing SFTs in preparation for system power off. The kernel will not allow any new IO calls to the FSD once it receives this first call, except from the swapper thread. The swapper thread will continue to call the FS_READ and FS_WRITE entry points to read and write the swap file. The swapper thread will not attempt to grow or shrink the swap file nor should the FSD reallocate it. The kernel will continue to allow FS_COMMIT and FS_FLUSHBUF calls from any thread. This call should not return from the FSD until disk data modifying calls have completed to insure that a thread already inside the FSD does not wake and change disk data.

After the first FS_SHUTDOWN call returns, the kernel will start committing SFTs. The FSD will see a commit for every SFT associated with it. During these FS_COMMIT calls, the FSD must flush any data associated with these SFTs to disk. The FSD must not allow any FS_COMMIT or FS_FLUSHBUF call to block permanently.

Once all of the SFTs associated with the FSD have been committed, FS_SHUTDOWN will be called with type == 1. This will tell the FSD to flush all buffers to disk. From this point, the FSD must not buffer any data destined for disk. Reads and writes to the swap file will continue, but the allocation of the swap file will not change. Once this call has completed, no file system corruption should occur if power is shut off.

FS_VERIFYUNCNAME Verify UNC server ownership

Purpose

Used to poll installed UNC FSDs to determine server ownership.

Calling Sequence

int far pascal FS_VERIFYUNCNAME (flag, pName) unsigned short flag; char far \ pName;

Where

flag

indicates which "pass" of the poll the FSD is being called.

flag == VUN_PASS1 (0x0000) indicates that this is a pass 1 poll.

flag == VUN_PASS2 (0x0001) indicates that this is a pass 2 poll.

pName

is a pointer to the ASCIIZ name of the server in UNC format.

The FSD does not need to verify this pointer.

Remarks

What the kernel expects from UNC FSDs for this entry point:

For pass 1, the FSD will be called and passed a pointer to the UNC server name. It is to respond immediately if it recongnizes(manages) the server with a NO_ERROR return code. This pass expects the that the FSD will be keeping tables in memory that contain the UNC names of the servers it is currently servicing. If the UNC name cannot be validated immediately, the FSD should respond with an error (non-zero) return code. The FSD SHOULD NOT send messages in an attempt to validate the server name.

For pass 2, the FSD is permitted to do whatever is reasonable, including sending LAN "are you there" messages, to determine if they are able to service the request for UNC server.

FS_WRITE Write to a file

Purpose

Write the specified number of bytes to a file from a buffer location.

Calling Sequence

int far pascal FS_WRITE (psffsi, psffsd, pDat, pLen, IOflag)

struct sffsi far \psffsi;struct sffsd far \psffsd;char far \pData;unsigned short far \pLen;unsigned shortIOflag;

Where

psffsi

is a pointer to the file-system-independent portion of an open file instance.

sfi_position is the location within the file where the data is to be written to. The FSD should update the sfi_position and sfi_size fields.

psffsd

is a pointer to the file-system-dependent portion of an open file instance.

pData

is the address of the application data area.

Addressing of this data area is not validated by the kernel (see FSH_PROBEBUF).

pLen

is a pointer to the length of the application data area.

On input, this is the number of bytes that are to be written. On output, this is the number of bytes successfully written. If the application data area is smaller than the length, no transfer is to take place. The FSD does not need to verify this pointer.

IOflag

indicates information about the operation on the handle.

IOflag == IOFL_WRITETHRU (0x0010) indicates write-through IOflag == IOFL_NOCACHE (0x0020) indicates no-cache

Remarks

If write is successful and is a file, the FSD should set ST_SWRITE and ST_PWRITE to make the kernel time stamp the last modification time in the SFT.

The FSD should return an error if an attempt is made to write beyond the end of the volume with a direct access device handle.

Of the information passed in IOflag, the write-through bit is a mandatory bit in that any data written to the block device must be put out on the medium before the device driver returns. The no-cache bit, on the other hand, is an advisory bit that says whether the data being transferred is worth caching or not. If an FSD supports file locking, it is responsible for checking if there are any locks on the file that should prevent the call from being executed. OS/2 will not do any lock checking if the FSA_LOCK bit is set in the FSD Attributes.

Chapter 3. FS Helper Functions

The following table summarizes the routines that make up the File System Helper interface between FSDs and the kernel.

| FS Helper Routine | Description |
|--|--|
| FSH_ADDSHARE | Add a name to the sharing set |
| FSH_BUFSTATE | REMOVED in OS/2 Version 2.0 |
| FSH_CALLDRIVER | Call Device Driver's Extended Strategy entry point |
| FSH_CANONICALIZE | Convert pathname to canonical form |
| FSH_CHECKEANAME | Check EA name validity |
| FSH_CRITERROR | Signal a hard error to the daemon |
| FSH_DEVIOCTL | Send IOCTL request to device driver |
| FSH_DOVOLIO | Volume-based sector-oriented transfer |
| FSH_DOVOLIO2 | Send volume-based IOCTL request to device driver. |
| FSH_EXTENDTIMESLICE | Request the kernel temporarily increase this thread's time slice |
| FSH_FINDCHAR | Find first occurrence of char in string |
| FSH_FINDDUPHVPB | Locates equivalent hVPBs |
| FSH_FLUSHBUF | REMOVED in OS/2 Version 2.0 |
| FSH_FORCENOSWAP | Force segments permanently into memory |
| FSH_GETBUF | REMOVED in OS/2 Version 2.0 |
| FSH_GETFIRSTOVERLAPBUF | REMOVED in OS/2 Version 2.0 |
| FSH_GETPRIORITY | Get current thread's I/O priority |
| FSH_GETVOLPARM | Get VPB data from VPB handle |
| FSH_INTERR | Signal an internal error |
| FSH_IOBOOST | Gives the current thread an I/O priority boost |
| FSH_IOSEMCLEAR | Clear an I/O-event semaphore |
| FSH_ISCURDIRPREFIX | Test for a prefix of a current directory |
| FSH_LOADCHAR | Load character from a string |
| FSH_NAMEFROMSFN | Get the full path name from an SFN |
| FSH_PREVCHAR | Move backward in string |
| FSH_PROBEBUF | User address validity check |
| FSH_QSYSINFO | Query system information |
| | Query if thread has oplock |
| | Query if thread is server thread Register a FSD with PERFVIEW |
| FSH_REGISTERPERFCTRS FSH_RELEASEBUF | REMOVED in OS/2 Version 2.0 |
| FSH_REMOVESHARE | Remove a name from the sharing set |
| FSH_SEGALLOC | Allocate a GDT or LDT segment |
| FSH_SEGFREE | Release a GDT or LDT segment |
| FSH_SEGREALLOC | Change segment size |
| FSH_SEMCLEAR | Clear a semaphore |
| FSH_SEMREQUEST | Request a semaphore |
| FSH_SEMSET | Set a semaphore |
| FSH_SEMSETWAIT | Set a semaphore and wait for clear |
| FSH_SEMWAIT | Wait for clear |
| FSH_SETVOLUME | force a volume to be mounted on the drive |
| FSH_STACKSPACE | Query avilable stack space |
| FSH_STORECHAR | Store character into string |
| FSH_UPPERCASE | Uppercase asciiz string |
| FSH_WILDMATCH | Match using OS/2 wildcards |
| FSH_YIELD | Yield CPU to higher priority threads |
| | |

FSDs are loaded as dynamic link libraries and may import services provided by the kernel. These services can be called directly by the file system, passing the relevant parameters.

|

I

No validation of input parameters is done unless otherwise specified. The FSD calls FSH_PROBEBUF, where appropriate, before calling the FS help routine.

When any service returns an error code, the FSD must return to the caller as soon as possible and return the specific error code from the helper to the FS router.

There are many deadlocks that may occur as a result of operations issued by FSDs. OS/2 provides no means whereby deadlocks between file systems and applications can be detected.

FSH_ADDSHARE Add a name to the share set

Purpose

This function adds a name to the currently active sharing set.

Calling Sequence

int far pascal FSH_ADDSHARE (pName, mode, hVPB, phShare)

| char far \setminus | pName; |
|-------------------------------|----------|
| unsigned short | mode; |
| unsigned short | hVPB; |
| unsigned long far \setminus | phShare; |

Where

pName

is a pointer to the ASCIIZ name to be added into the share set.

The name must be in canonical form: no '.' or '..' components, uppercase, no meta characters, and full path name specified.

mode

is the sharing mode and access mode as defined in the DosOpen API.

All other bits (direct open, write-through, etc.) must be zero.

hVPB

is the handle to the volume where the named object is presumed to exist.

phShare

is the pointer to the location where a share handle is stored. This handle may be passed to FSH_REMOVESHARE.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_SHARING_VIOLATION

the file is open with a conflicting sharing/access mode.

ERROR_TOO_MANY_OPEN_FILES

there are too many files open at the present time.

ERROR_SHARING_BUFFER_EXCEEDED

there is not enough memory to hold sharing information.

ERROR_INVALID_PARAMETER

invalid bits in mode.

ERROR_FILENAME_EXCED_RANGE

path name is too long.

Remarks

Do not call FSH_ADDSHARE for character devices.

FSH_ADDSHARE may block.

FSH CALLDRIVER Call Device Driver's Extended Strategy entry point

Purpose

This routine allows FSDs to call a device driver's Extended Strategy entry point.

Calling Sequence

int far pascal FSH_CALLDRIVER (pPkt, hVPB, fControl)

void far \ pPkt; unsigned short hVP unsigned short fControl;

hVPB;

Where

pPkt

is a pointer to device driver Extended strategy request packet. See OS/2 Version 3.0 Physical Device Driver Reference for the packet format

hVPB

is the volume handle for the source of I/O.

fControl

is the bit mask of pop-up control actions:

Bit 0 off indicates volume change pop-up desired

Bit 0 on indicates no volume change pop-up

All other bits are reserved and must be zero.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_VOLUME_CHANGED

is an indication that removable media volume change has occured.

ERROR_INVALID_PARAMETER

the fControl flag word has reserved bits on.

Remarks

This routine should be called for any Extended strategy requests going to a drive that has removable media.

For a detailed description of the Extended Strategy request interface please see the OS/2 Version 3.0 Physical Device Driver Reference.

FSH_CALLDRIVER may block.

Note: OS/2 does not validate input parameters. Therefore, an FSD should call FSH_PROBEBUF where appropriate.

All data buffers that are to be accessed by the device driver should be locked by the FSD prior to using this call. The current way to accomplish this is to call the Device Driver Helpers VirtToLin followed by VMLock. See OS/2 Version 3.0 Phys*ical Device Driver Reference* for a description of these calls. This helper basically does a check to see if the volume has not been changed and then calls the device driver. The file system is responsible for the validity of the request packet. In addition, if the file system wishes to correctly support the DosSetVerify API, the FSD should use FSH_QSYSINFO to determine the state of the verify bit and set the write command accordingly.

FSH_CANONICALIZE Convert a path name to a canonical form

Purpose

This function converts a path name to a canonical form by processing '.'s and '..'s, uppercasing, and prepending the current directory to non-absolute paths.

Calling Sequence

int far pascal FSH_CANONICALIZE (pPathName, cbPathBuf, pPathBuf, pFlags)

pPathName;

char far \pPathName;unsigned shortcbPathBuf;char far \pPathBuf;unsigned short far \pFlags;

Where

pPathName

is a pointer to the ASCIIZ path name to be canonicalized.

cbPathBuf

is the length of path name buffer.

pPathBuf

is the pointer to the buffer into which to copy the canonicalized path.

pFlags

is the pointer to flags returned to the FSD.

Flags == 0x0040 indicates a non-8.3 filename format. All other values are reserved.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_PATH_NOT_FOUND

is an invalid path name-too many '..'s

ERROR_BUFFER_OVERFLOW

the path name is too long.

Remarks

This routine processes DBCS characters properly.

The FSD is responsible for verifying the string pointers and checking for segment boundaries.

FSH_CANONICALIZE should be called for names passed into the FSD raw data packets. For example, names passed to FS_FSCTL in the parameter area should be passed to FSH_CANONICALIZE. This routine does not need to be called for explicit names passed to the FSD, that is, the name passed to FS_OPENCREATE.

If the canonicalized name is being created as a file or directory, the non-8.3 attribute in the directory entry should be set according to the value returned in pFlags.

FSH_CHECKEANAME Check for valid EA name

Purpose

Check extended attribute name validity.

Calling Sequence

int far pascal FSH_CHECKEANAME (iLevel, cbEAName, szEAName)

unsigned short iLevel; unsigned long cbEAName; char far \ szEAName;

Where

iLevel

is the extended attributes name checking level.

iLevel = 0x0001 indicates OS/2 Version 3.0 name checking.

cbEAName

is the length of the extended attribute name, not including terminating NUL.

szEAName

is the extended attribute name to check for validity.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INVALID_NAME

pathname contains invalid or wildcard characters, or is too long.

ERROR_INVALID_PARAMETER

invalid level.

Remarks

This routine processes DBCS characters properly.

The set of invalid characters for EA names is the same as that for filenames. In OS/2 Version 3.0, the maximum length of an EA name, not including the terminating NUL, is 255 bytes. The minimum length is 1 byte.

The FSD is responsible for verifying the string pointers and checking for segment boundaries.

FSH_CHECKEANAME should be called for extended attribute names passed to the FSD.

FSH_CRITERROR Signal hard error to daemon

Purpose

This function signals a hard error to the daemon.

Calling Sequence

int far pascal FSH_CRITERROR (cbMessage, pMessage, nSubs, pSubs, fAllowed)

unsigned short cbMessage; char far \ pMessage; unsigned short nSubs; char far \ pSubs; unsigned short fAllowed;

Where

cbMessage

is the length of the message template.

pMessage

is the pointer to the message template.

This may contain replaceable parameters in the format used by the message retriever.

nSubs

is the number of replaceable parameters.

pSubs

is the pointer to the replacement text.

The replacement text is a packed set of ASCIIZ strings.

fAllowed

is the bit mask of allowed actions:

CE_ALLFAIL, Bit 0x0001 on indicates FAIL allowed

CE_ALLABORT, Bit 0x0002 on indicates ABORT allowed

CE_ALLRETRY, Bit 0x0004 on indicates RETRY allowed

CE_ALLIGNORE, Bit 0x0008 on indicates IGNORE allowed

CE_ALLACK, Bit 0x0010 on indicates ACKNOWLEDGE only allowed.

All other bits are reserved and must be zero. If bit 0x0010 is set, and any or some of bits 0x0001 to 0x0008 are also set, bit 0x0010 will be ignored.

Returns

This function returns the action to be taken:

CE_RETIGNORE, 0x0000 - ignore

CE_RETRETRY, 0x0001 - retry

CE_RETFAIL, 0x0003 - fail

CE_RETACK, 0x0004 - continue

Remarks

If the user responds with an action that is not allowed, it is treated as FAIL. If FAIL is not allowed, it is treated as ABORT. ABORT is always allowed.

When ABORT is the final action, OS/2 does not return this as an indicator; it returns a FAIL. The actual ABORT operation is generated when this thread of execution is about to return to user code.

The maximum length of the template is 128 bytes, including the NUL. The maximum length of the message with text substitutions is 512 bytes. The maximum number of substitutions is 9.

If any action other than retry is selected for a given hard error popup, then any subsequent popups (within the same API call) will be automatically failed; a popup will not be done. This means that (except for retries) there can be at most one hard error popup per call to the FSD. And, if the kernel generates a popup, then the FSD cannot create one.

FSH_CRITERROR will fail automatically if the user application has set autofail, or if a previous hard error has occurred.

FSH_CRITERROR may block.

FSH_DEVIOCTL Send IOCTL request to device driver

Purpose

This function sends an IOCTL request to a device driver.

Calling Sequence

int far pascal FSH_DEVIOCTL (flag, hDev, sfn, cat, func, pParm, cbParm, pData, cbData)

| unsigned short | flag; |
|----------------------|---------|
| unsigned long | hDev; |
| unsigned short | sfn; |
| unsigned short | cat; |
| unsigned short | func; |
| char far \setminus | pParm; |
| unsigned short | cbParm; |
| char far \setminus | pData; |
| unsigned short | cbData; |
| | |

Where

flag

indicates whether the FSD initiated the call or not.

IOflag == 0x0000 indicates that the FSD is just passing user pointers on to the helper.

IOflag == 0x0001 indicates that the FSD initiated the DevIOCtl call as opposed to passing a DevIOCtl that it had received. All other bits are reserved.

hDev

is the device handle obtained from VPB

sfn

is the system file number from open instance that caused the FSH_DEVIOCTL call.

This field should be passed unchanged from the sfi_selfsfn field. If no open instance corresponds to this call, this field should be set to 0xFFFF.

cat

is the category of IOCTL to perform.

func

is the function within the category of IOCTL.

pParm

is the long address to the parameter area.

cbParm

is the length of the parameter area.

pData

is the long address to the data area.

cbData

is the length of the data area.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INVALID_FUNCTION

indicates the function supplied is incompatible with the category and device handle supplied.

ERROR_INVALID_CATEGORY

indicates the category supplied is incompatible with the function and device handle supplied.

Device driver error code

Remarks

The only category currently supported for this call is 8, which is for the logical disk. FSDs call FSH_DEVIOCTL to control device driver operation independently from I/O operations. This is typically in filtering DosDevIOCtl requests when passing the request on to the device driver.

An FSD needs to be careful of pointers to buffers that are passed to it from FS_IOCTL, and what it passes to FSH_DEVIOCTL. It is possible that such pointers may be real mode pointers if the call was made from the DOS mode. In any case, the FSD must indicate whether it initiated the DevIOCtl call, in which case the kernel can assume that the pointers are all protect mode pointers, or if it is passing user pointers on to the FSH_DEVIOCTL call, in which case the mode of the pointers will depend on whether this is the DOS mode or not. An important thing to note is that the FSD must not mix user pointers with its own pointers when using this helper.

FSH_DEVIOCTL may block.

FSH_DOVOLIO Transfer volume-based sector-oriented I/O

Purpose

This function performs I/O to the specified volume.

Calling Sequence

int far pascal FSH_DOVOLIO (operation, fAllowed, hVPB, pData, pcSec, iSec)

| unsigned short | operation; |
|------------------------|------------|
| unsigned short | fAllowed; |
| unsigned short | hVPB; |
| char far \setminus | pData; |
| unsigned short far $\$ | pcSec; |
| unsigned long | iSec; |

Where

operation

is the bit mask indicating read/read-bypass/write/write-bypass, and verify-afterwrite/write-through and no-cache operation to be performed.

DVIO_OPREAD, Bit 0x0001 off indicates read. DVIO OPWRITE, Bit 0x0001 on indicates write. Bit 0x0002 off indicates no cache bypass. DVIO_OPBYPASS, Bit 0x0002 on indicates cache bypass. Bit 0x0004 off indicates no verify-after-write operation. DVIO OPVERIFY. Bit 0x0004 on indicates verify-after-write operation. Bit 0x0008 off indicates errors signalled to the hard error daemon. DVIO_OPHARDERR, Bit 0x0008 on indicates hard errors will be returned directly. Bit 0x0010 off indicates I/O is not write-through. DVIO_OPWRTHRU, Bit 0x0010 on indicates I/O is write-through. Bit 0x0020 off indicates data for this I/O should probably be cached. DVIO OPNCACHE, Bit 0x0020 on indicates data for this I/O should probably not be cached. Bit 0x0040 off indicate that memory should be locked. DVIO_OPRESMEM, Bit 0x0040 on indicates the memory should not be locked. All other bits are reserved and must be zero.

The difference between the cache bypass and the no cache bits is in the type of request packet that the device driver will see. With cache bypass, it will get a packet with command code 24, 25, or 26. With no cache, it will get the extended packets for command codes 4, 8, or 9. The advantage of the latter is that the write-through bit can also be sent to the device driver in the same packet, improving the functionality at the level of the device driver.

fAllowed

is a bit mask indicating allowed actions:

DVIO_ALLFAIL, Bit 0x0001 on indicates FAIL allowed DVIO_ALLABORT, Bit 0x0002 on indicates ABORT allowed DVIO_ALLRETRY, Bit 0x0004 on indicates RETRY allowed DVIO_ALLIGNORE, Bit 0x0008 on indicates IGNORE allowed DVIO_ALLACK, Bit 0x0010 on indicates ACKNOWLEDGE only allowed

If this bit is set, none of the other bits may be set.

All other bits are reserved and must be set to zero.

hVPB

is the volume handle for the source of I/O.

pData

is the long address of the user transfer area.

pcSec

is the pointer to the number of sectors to be transferred.

On return, this is the number of sectors successfully transferred.

iSec

is the sector number of the first sector of the transfer.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_PROTECTION_VIOLATION

indicates the supplied address/length is invalid.

ERROR_UNCERTAIN_MEDIA

indicates the device driver can no longer reliably tell if the media has been changed.

This occurs only within the context of an FS_MOUNT call.

ERROR_TRANSFER_TOO_LONG

indicates the transfer is too long for the device.

Device-driver/device-manager errors listed /DDERR/

Remarks

This function formats a device driver request packet for the requested I/O, locks the data transfer region, calls the device driver, and reports any errors to the hard error daemon before returning to the FSD. Any retries indicated by the hard error daemon or actions indicated by DosError are done within the call to FSH_DOVOLIO.

FSH_DOVOLIO may be used at all times within the FSD. When called within the scope of a FS_MOUNT call, it applies to the volume in the drive without regard to which volume it may be. However, since volume recognition is not complete until the FSD returns to the FS_MOUNT call, the FSD must be careful when an ERROR_UNCERTAIN_MEDIA is returned. This indicates the media has gone uncertain while we are trying to identify the media in the drive. This may indicate the volume that the FSD was trying to recognize was removed. In that case, the FSD must release any resources attached to the hVPB passed in the FS_MOUNT call and return ERROR_UNCERTAIN_MEDIA to the FS_MOUNT call. This will direct the volume tracking logic to restart the mount process.

OS/2 will validate the user transfer area for proper access and size and will lock the segment.

Verify-after-write specified on a read is ignored.

On 80386 processors, FSH_DOVOLIO will take care of memory contiguity requirements of device drivers. It is advisable, therefore, that FSDs use FSH_DOVOLIO instead of calling device drivers directly. This will improve performance of FSDs running on 80386 processors.

FSH_DOVOLIO may block.

FSH_DOVOLIO2 Send volume-based IOCTL request to device driver

Purpose

This function is an FSD call that controls device driver operation independently from I/O operations.

Calling Sequence

int far pascal FSH_DOVOLIO2 (hDev, sfn, cat, func, pParm, cbParm, pData, cbData)

unsigned long hDev; unsigned short sfn; unsigned short cat; unsigned short func; char far $\$ pParm; unsigned short cbParm; char far $\$ pData; unsigned short cbData;

Where

hDev

is the device handle obtained from VPB

sfn

is the system file number from the open instance that caused the FSD_DEVIOCTL call.

This field should be passed unchanged from the sfi-selfsfn field. It no open instance corresponds to this call, this field should be set to 0xFFFF.

cat

is the category of IOCTL to perform.

func

is the function within the category of IOCTL.

pParm

is the long address to the parameter area.

cbParm

is the length of the parameter area.

pData

is the long address to the data area.

cbData

is the length of the data area.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INVALID_FUNCTION

indicates the function supplied is incompatible with the category and the device handle supplied.

ERROR_INVALID_CATEGORY

indicates the category supplied is incompatible with the function and the device handle supplied.

Device-driver/device-manager errors listed /DDERR/

Remarks

This routine supports volume management for IOCTL operations. Any errors are reported to the hard error daemon before returning to the FSD. Any retries indicated by the hard error daemon or actions indicated by DosError are done within the call to FSH_DOVOLIO2.

The purpose of this routine is to enable volume tracking with IOCTLs. It is not available at the API level.

FSH_DOVOLIO2 may block.

System does normal volume checking for this request.

FSH_EXTENDTIMESLICE Notify kernel that temporarily increasing this thread's time slice is advisable.

Purpose

Notify kernel to temporarily increasing this thread's time slice.

This helper is new to OS/2 3.0. It is currently being used internally if a cache hit occurred to temporarily increase the current thread's time slice because the probability is high that additional I/O requests will also be in the cache. This resulted in a performance gain.

This call needs to be used carefully. Improper use can result in performance degradation in different environments. In addition, OS/2 development believes that there is a good probability that the function or calling parameters for this helper may need modification for optimal performance in future releases. Consequently, use this helper with appropriate care- it may result in otherwise unnecessary level sensitivity to future releases.

Calling Sequence

int far pascal FSH_EXTENDTIMESLICE ()

Where

There are no parameters to this helper.

Returns

The return code may be ignored.

FSH_FINDCHAR Find first occurrence of character in string

Purpose

This function provides the mechanism to find the first occurrence of any one of a set of characters in an ASCIIZ string, taking into account DBCS considerations.

Calling Sequence

int far pascal FSH_FINDCHAR (nChars, pChars, ppStr)

 $\begin{array}{ll} \text{unsigned short} & n\text{Chars;} \\ \text{char far} \setminus & p\text{Chars;} \\ \text{char far} \far \setminus & pp\text{Str;} \end{array}$

Where

nChars

is the number of characters in the search list.

pChars

is the array of characters to search for. These cannot be DBCS characters. The NUL character cannot be searched for.

ppSTR

is the pointer to the character pointer where the search is to begin. This pointer is updated upon return to point to the character found. This must be an ASCIIZ string.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_CHAR_NOT_FOUND

indicates none of the characters were found.

Remarks

The search will continue until a matching character is found or the end of the string is found.

The FSD is responsible for verifying the string pointers and checking for segment boundaries.

FSH_FINDDUPHVPB Locate equivalent hVPB

Purpose

This function provides the mechanism to identify a previous instance of a volume during the FS_MOUNT process.

Calling Sequence

int far pascal FSH_FINDDUPHVPB (hVPB, phVPB)

unsigned short hVPB; unsigned short far \ phVPB;

Where

hVPB

is the handle to the volume to be found.

phVPB

is the pointer to where the handle of matching volume will be stored.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_NO_ITEMS

indicates there is no matching hVPB.

Remarks

When OS/2 is recognizing a volume, it calls the FSD to mount the volume. At this point, the FSD may elect to allocate storage and buffer data for that volume. The mount process will allocate a new VPB whenever the media becomes uncertain, that is, when the device driver recognizes it can no longer be certain the media is unchanged. This VPB cannot be collapsed with a previously allocated VPB, because of a reinsertion of media, until the FS_MOUNT call returns. The previous VPB, however, may have some cached data that must be updated from the media (the media may have been written while it was removed) FSD_FINDDUPHVPB allows the FSD to find this previous occurrence of the volume in order to update the cached information for the old VPB. Remember the newly created VPB will be unmounted if there is another, older VPB for that volume.

FSH_FORCENOSWAP Force segments permanently into memory

Purpose

This function permanently forces segments into memory.

Calling Sequence

int far pascal FSH_FORCENOSWAP (sel)

unsigned short sel;

Where

sel

is the selector that is to be made non-swappable.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INVALID_ACCESS

indicates the selector is invalid.

ERROR_INVALID_DENIED

indicates the selector is invalid or the sector belongs to another process.

ERROR_DIRECT_ACCESS_HANDLE

indicates the handle does not refer to a segment.

ERROR_NOT_ENOUGH_MEMORY

indicates there is not enough physical memory to make a segment non-swappable.

ERROR_SWAP_TABLE_FULL

indicates the attempt to grow the swap file failed.

ERROR_SWAP_FILE_FULL

indicates the attempt to grow the swap file failed.

ERROR_PMM_INSUFFICIENT_MEMORY

indicates the attempt to grow the swap file failed.

Remarks

An FSD may call FSH_FORCENOSWAP to force segments to be loaded into memory and marked non-swappable. All segments both in the load image of the FSD and those allocated via FSH_SEGALLOC are eligible to be marked. There is no way to undo the effect of FSH_FORCENOSWAP.

If an FSD is notified it is managing the swapping media, it should make this call for the necessary segments.

An FSD should be prepared to see multiple swapping files on more than one volume in 80386 processors and in future releases of OS/2.

FSH_FORCENOSWAP may block.

FSH_GETPRIORITY Get current thread's I/O priority

Purpose

This function allows an FSD to retrieve the I/O priority of the current thread.

Calling Sequence

int far pascal FSH_GETPRIORITY (void)

Returns

This function returns the I/O priority of the current thread:

0x0000 - background

0x1111 - foreground

Remarks

FSH_GETPRIORITY will not block.

FSH_GETVOLPARM Get VPB data from VPB handle

Purpose

This function allows an FSD to retrieve file-system-independent and file-systemdependent data from a VPB. Since the FS router passes in a VPB handle, individual FSDs need to map the handle into pointers to the relevant portions.

Calling Sequence

void far pascal FSH_GETVOLPARM (hVPB, ppVPBfsi, ppVPBfsd)

unsigned short hVPB; struc vpfsi far \far \ ppVPBfsi; struc vpfsd far \far \ ppVPBfsd;

Where

hVPB

is the volume handle of interest.

ppVPBfsi

indicates the location where the pointer to file-system-independent data is stored.

ppVPBfsd

indicates the location where the pointer to file-system-dependent data is stored.

Returns

There are no error returns.

Remarks

FSH_GETVOLPARM will not block.

FSH_INTERR Signal an internal error

Purpose

This function signals an internal error.

Calling Sequence

void far pascal FSH_INTERR (pMsg, cbMsg)

char far \ pMsg; unsigned short cbMsg;

Where

pMsg

is a pointer to the message text.

cbMsg

is the length of the message text.

Returns

There are no error returns.

Remarks

For reliability, if an FSD detects an internal inconsistency during normal operation, the FSD shuts down the system as a whole. This is the safest thing to do since it is not clear if the system as a whole is in a state that allows normal execution to continue.

When an FSD calls FSH_INTERR, the address of the caller and the supplied message is displayed on the console. The system then halts.

The code used to display the message is primitive. The message should contain ASCII characters in the range 0x20-0x7E, optionally with 0x0D and 0x0A to break the text into multiple lines.

The FSD must preface all such messages with the name of the file system.

The maximum message length is 512 characters. Messages longer than this are truncated.

FSH_IOBOOST Gives the current thread an I/O priority boost

Purpose

This function allows an FSD to boost the current thread's I/O priority after a I/O request.

Calling Sequence

void far pascal FSH_IOBOOST (void)

Returns

There are no error returns.

Remarks

FSH_IOBOOST will not block.

FSH_IOSEMCLEAR Clear an I/O event semaphore

Purpose

This function allows an FSD to clear the I/O event semaphore that is a part of the Extended Strategy request packet.

Calling Sequence

int far pascal FSH_IOSEMCLEAR (pSem)

Where

pSem

is the handle to the I/O event semaphore.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_EXCL_ALREADY_OWNED

the exclusive semaphore is already owned.

ERROR_PROTECTION_VIOLATION

the semaphore is inaccessible.

Remarks

FSH_IOSEMCLEAR may block.

For a detailed description of the Extended Strategy request interface please see the *OS/2 Version 3.0 Physical Device Driver Reference*.

FSH_ISCURDIRPREFIX Test for a prefix of a current directory

Purpose

This function allows FSDs to disallow any modification of any directory that is either a current directory of some process or the parent of any current directory of some process. This is necessary because the kernel manages the text of each current directory for each process.

Calling Sequence

int far pascal FSH_ISCURDIRPREFIX (pName)

 $char \; far \, \backslash \qquad pMsg;$

Where

pName

is a pointer to the path name.

The name must be in canonical form, that is, no '.' or '..' components, uppercase, no meta characters, and full path name specified.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_CURRENT_DIRECTORY

the specified path is a prefix of or is equal to the current directory of some process.

If the current directory is the root and the path name is "d:\," ERROR_CURRENT_DIRECTORY will be returned.

Remarks

FSH_ISCURDIRPREFIX takes the supplied path name, enumerates all current directories in use, and tests to see if the specified path name is a prefix or is equal to some current directory.

FSH_ISCURDIRPREFIX may block.

FSH_LOADCHAR Load a character from a string

Purpose

This function provides the mechanism for loading a character from a string, taking into account DBCS considerations.

Calling Sequence

void far pascal FSH_LOADCHAR (ppStr, pChar)

 $\begin{array}{ll} char \ far \ far \ ppStr;\\ unsigned \ short \ far \ pChar; \end{array}$

Where

ppStr

is a pointer to the character pointer of a string.

The character at this location will be retrieved and this pointer will be updated.

pChar

is a pointer to the character returned.

If character is non-DBCS, the first byte will be the character and the second byte will be zero.

Returns

There are no error returns.

Remarks

FSH_NAMEFROMSFN Get the full path name from an SFN.

Purpose

This call allows an FSD to retrieve the full path name for an object to which an SFN refers.

Calling Sequence

int far pascal FSH_NAMEFROMSFN (sfn, pName, pcbName)

unsigned short sfn; char far \ pName; unsigned short far \pcbName;

Where

sfn

is the system file number of a file instance, obtained from the sfi_selfsfn field of the file-system-independent part of the SFT for the object.

pName

is the location of where the returned full path name is to be stored.

pcbName

is the location of where the FSD places the size of the buffer pointed to by pName. On return, the kernel will fill this in with the length of the path name. This length does not include the terminating null character. The size of the buffer should be long enough to hold the full path name, or else an error will be returned.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INVALID_HANDLE

the SFN is invalid.

ERROR_BUFFER_OVERFLOW

the buffer is too short for the returned path.

Remarks

FSH_NAMEFROMSFN will not block.

Note:

OS/2 does not validate input parameters; the FSD should call FSH_PROBEBUFF where appropriate.

FSH_PREVCHAR Decrement a character pointer

Purpose

This function provides the mechanism for decrementing a character pointer, taking into account DBCS considerations.

Calling Sequence

void far pascal FSH_PREVCHAR (pBeg, ppStr)

 $\begin{array}{ll} char \ far \setminus & pBeg;\\ char \ far \setminus far \setminus & ppStr; \end{array}$

Where

pBeg

is a pointer to the beginning of a string.

ppStr

is a pointer to the character pointer of a string.

The value is decremented appropriately upon return. If it is at the beginning of a string, the pointer is not decremented. If it points to the second byte of a DBCS character, it will be decremented to point to the first byte of the character.

Returns

There are no error returns.

Remarks

The FSD is responsible for verifying the string pointer and checking for segment boundaries.

FSH_PROBEBUF Check user address validity

Purpose

This function provides the mechanism for performing validity checks on arbitrary pointers to data that users may pass in.

Note: FSDs must check on these pointers before using them.

Calling Sequence

int far pascal FSH_PROBEBUF (operation, pdata, cbData)

unsigned short operation; char far \ pData; unsigned short cbData;

Where

operation

indicates whether read or write access is desired.

operation == PB_OPREAD, (0x00) indicates read access is to be checked. operation == PB_OPWRITE, (0x01) indicates write access is to be checked.

All other values are reserved.

pData

is the starting address of user data.

cbData

is the length of user data. If cbData is 0, a length of 64K is indicated.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_PROTECTION_VIOLATION

indicates access to the indicated memory region is illegal (access to the data is inappropriate or the user transfer region is partially or completely inaccessible).

Remarks

Because users may pass in arbitrary pointers to data, FSDs must perform validity checks on these pointers before using them. Because OS/2 is multi-threaded, the addressability of data returned by FSH_PROBEBUF is only valid until the FSD blocks. Blocking, either explicitly or implicitly allows other threads to run, possibly invalidating a user segment. FSH_PROBEBUF must, therefore, be reapplied after every block.

FSH_PROBEBUF provides a convenient method to assure a user transfer address is valid and present in memory. Upon successful return, the user address may be treated as a far pointer and accessed up to the specified length without either blocking or faulting. This is guaranteed until the FSD returns or until the next block.

If FSH_PROBEBUF detects a protection violation, the process is terminated as soon as possible. The OS/2 kernel kills the process once it has exited from the FSD.

On 80386 processors, FSH_PROBEBUF ensures all touched pages are physically present in memory so the FSD will not suffer an implicit block due to a page fault. However, FSH_PROBEBUF does NOT guarantee the pages will be physically contiguous in memory because FSDs are not expected to do DMA.

FSH_PROBEBUF may block.

FSH_QSYSINFO Query system information

Purpose

This function queries the system about dynamic system variables and static system variables not returned by DosQSysInfo.

Calling Sequence

int far pascal FSH_QSYSINFO (index, pData, cbData)

unsigned short index; char far \ pData; unsigned short cbData;

Where

index

is the variable to return.

index == QSI_SECSIZE (0x01) indicates maximum sector size. This will be returned in an unsigned short field.

index == QSI_PROCID (0x02) indicates process identity. The data returned will be as follows:

struct

unsigned short PID; unsigned short UID; unsigned short PDB;

index == $QSI_THREADNO$ (0x03) indicates absolute thread number for the current thread. This will be returned in an unsigned short field.

index == QSI_VERIFY (0x04) indicates verify on write flag for the process. This will be returned in an unsigned char (byte) field. Zero means verify is off, non-zero means it is on.

pData

is the long address to the data area.

cbData

is the length of the data area.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INVALID_PARAMETER

the index is invalid.

ERROR_BUFFER_OVERFLOW

the specified buffer is too short for the returned data.

Remarks

FSH_QUERYOPLOCKQuery if the running thread has an oplock

Purpose

This function queries if the running thread has an oplock.

Calling Sequence

int far pascal FSH_QUERYOPLOCK (void)

Returns

This function returns as status indicator for whether the thread has an oplock or not.

0xffff - thread has an oplock

0x0000 - thread does not have an oplock

FSH_QUERYSERVERTHREAD Query if the current thread is a server thread

Purpose

L

Query if the current thread is a server thread.

Calling Sequence

int far pascal FSH_QUERYSERVERTHREAD (void)

Returns

This function returns a flag indicating whether the thread is a server thread.

0xffff - thread is a server thread

0x0000 - thread is not a server thread

FSH_REGISTERPERFCTRS Register a FSD with PERFVIEW

Purpose

This function allows the FSD to register with the PERFVIEW product. The FSD passes pointers to its counter data and text blocks.

Calling Sequence

int far pascal FSH_REGISTERPERFCTRS (pDataBlk, pTextBlk, fsFlags)

void far \ pDataBlk; void far \ pTextBlk; unsigned short fsFlags;

Where

pDataBlk

is a pointer to the data block where the actual counters reside.

pTextBlk

is a pointer to the block that contains instance and name information about counters in the associated DataBlk.

fsFlags

indicates what type of addressing is going to be used.

RPC_16BIT (0x0000) indicates 16:16 pointers RPC_32BIT (0x0001) indicates 0:32 pointers

All other bits are reserved and must be zero.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INVALID_PARAMETER

the flag word is invalid.

ERROR_PVW_INVALID_COUNTER_BLK

the specified buffer is not in the correct PERFVIEW data block format

ERROR_PVW_INVALID_TEXT_BLK

the specified buffer is not in the correct PERFVIEW text block format

Remarks

For a detailed description of the PERFVIEW interface and its associated data structures please see the *OS/2 Version 3.0 PERFVIEW OEMI Document*.

FSH_REGISTERPERFCTRS may block.

FSH_REMOVESHARE Remove a shared entry

Purpose

This function removes a previously-entered name from the sharing set.

Calling Sequence

void far pascal FSH_REMOVESHARE (hShare)

unsigned long hShare;

Where

hShare

is a share handle returned by a prior call to FSH_ADDSHARE.

Returns

There are no error returns.

Remarks

When a call to FSH_REMOVESHARE has been issued, the share handle is no longer valid.

FSH_REMOVESHARE may block.

FSH_SEGALLOC Allocate a GDT or LDT segment

Purpose

This function allocates a GDT or LDT selector. The selector will have read/write access. An FSD may call this function.

Calling Sequence

int far pascal FSH_SEGALLOC (flags, cbSeg, pSel)

unsigned short flags; unsigned long cbSeg; unsigned short far \ pSel;

Where

flags

indicate GDT/LDT, protection ring, swappable/non-swappable.

Bit 0x0001 off indicates GDT selector returned. SA_FLDT (0x0001), bit 0x0001 on indicates LDT selector returned. Bit 0x0002 off indicates non-swappable memory. SA_FSWAP (0x0002), bit 0x0002 on indicates swappable memory. Bits 13 and 14 are the desired ring number. SA_FRINGMASK (0x6000) may be used to isolate it.

All other bits are reserved and must be zero.

cbSeg

is the length of the segment.

pSel

is the far address of the location where the allocated selector will be stored.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INTERRUPT

the current thread received a signal.

ERROR_INVALID_PARAMETER

the reserved bits in flags are set or requested size is too large.

ERROR_NOT_ENOUGH_MEMORY

too much memory is allocated.

Remarks

It is strongly suggested that FSDs allocate all their data at protection level 0 for maximum protection from user programs.

GDT selectors are a scarce resource; the FSD must be prepared to expect an error for allocation of a GDT segment. The FSD should limit itself to a maximum of 10 GDT segments. It is suggested that a large segment be allocated for each type of data and divided into per-process records.

FSH_SEGALLOC may block.

Take care to avoid deadlocks between swappable segments and swapper requests.

FSH_SEGFREE Release a GDT or LDT segment

Purpose

This function releases a GDT or LDT segment previously allocated with FSH_SEGALLOC or loaded as part of the FSD image.

Calling Sequence

int far pascal FSH_SEGFREE (sel)

unsigned short sel;

Where

sel

is the selector to be freed.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INVALID_ACCESS

the selector is invalid.

Remarks

FSH_SEGFREE may block.

FSH_SEGREALLOC Change segment size

Purpose

This function changes the size of a segment previously allocated with FSH_SEGALLOC or loaded as part of the FSD image.

Calling Sequence

int far pascal FSH_SEGREALLOC (sel, cbSeg)

unsigned short sel; unsighed long cbSeg;

Where

sel

is the selector to be changed.

cbSeg

is the new size to set for the segment.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_NOT_ENOUGH_MEMORY

too much memory is allocated.

ERROR_INVALID_ACCESS

the selector is invalid

Remarks

The segment may be grown or shrunk. The segment may be moved in the process. When grown, the extra space is uninitialized.

FSH_SEGREALLOC may block.

FSH_SEMCLEAR Clear a semaphore

Purpose

This function allows an FSD to release a semaphore that was previously obtained on a call to FSH_SEMREQUEST.

Calling Sequence

int far pascal FSH_SEMCLEAR (pSem)

void far \setminus pSem;

Where

pSem

is the handle to the system semaphore or the long address of the ram semaphore.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_EXCL_ALREADY_OWNED

the exclusive semaphore is already owned.

ERROR_PROTECTION_VIOLATION

the semaphore is inaccessible.

Remarks

FSH_SEMCLEAR may block.

FSH_SEMREQUEST Request a semaphore

Purpose

This function allows an FSD to obtain exclusive access to a semaphore.

Calling Sequence

int far pascal FSH_SEMREQUEST (pSem, cmsTimeout)

void far \ pSem; unsigned long cmsTimeout;

Where

pSem

is the handle to the system semaphore or the long address of the ram semaphore.

cmsTimeout

is the number of milliseconds to wait.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INTERRUPT

the current thread received a signal.

ERROR_SEM_TIMEOUT

the timeout expired without gaining access to the semaphore.

ERROR_SEM_OWNER_DIED

the owner of the semaphore died.

ERROR_TOO_MANY_SEM_REQUESTS

there are too many semaphore requests in progress.

ERROR_PROTECTION_VIOLATION

the semaphore is inaccessible.

Remarks

The timeout value of 0xFFFFFFF indicates an indefinite timeout.

The caller may receive access to the semaphore after the timeout period has expired without receiving an ERROR_SEM_TIMEOUT. Semaphore timeout values, therefore, should not be used for exact timing and sequencing.

FSH_SEMREQUEST may block.

Note: The error, ERROR_INTERRUPT, is not usually a critical error. Unless the FSD needs to do some additional processing if a signal has occurred, it is normal to just retry the FSH_SEMREQUEST call. It is extremely important to check and handle the return codes for this call correctly.

FSH_SEMSET Set a semaphore

Purpose

This function allows an FSD to set a semaphore unconditionally.

Calling Sequence

int far pascal FSH_SEMSET (pSem)

void far \setminus pSem;

Where

pSem

is the handle to the system semaphore or the long address of the ram semaphore.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_INTERRUPT

the current thread received a signal.

ERROR_EXCL_SEM_ALREADY_OWNED

the exclusive semaphore is already owned.

ERROR_TOO_MANY_SEM_REQUESTS

there are too many semaphore requests in progress.

ERROR_PROTECTION_VIOLATION

the semaphore is inaccessible.

Remarks

FSH_SEMSET may block.

FSH_SEMSETWAIT Set a semaphore and wait for clear

Purpose

This function allows an FSD to wait for an event. The event is signalled by a call to FSH_SEMCLEAR.

Calling Sequence

int far pascal FSH_SEMSETWAIT (pSem, cmsTimeout)

void far \ pSem; unsigned long cmsTimeout;

Where

pSem

is the handle to the system semaphore or the long address of the ram semaphore.

cmsTimeout

is the number of milliseconds to wait.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_SEM_TIMEOUT

the timeout expired without gaining access to the semaphore.

ERROR_INTERRUPT

the current thread received a signal.

ERROR_EXCL_SEM_ALREADY_OWNED

the exclusive semaphore is already owned.

ERROR_PROTECTION_VIOLATION

the semaphore is inaccessible.

Remarks

The caller may return after the timeout period has expired without receiving an ERROR_SEM_TIMEOUT. Semaphore timeout values, therefore, should not be used for exact timing and sequence.

FSH_SEMSETWAIT may block.

FSH_SEMWAIT Wait for clear

Purpose

This function allows an FSD to wait for an event. The event is signalled by a call to FSH_SEMCLEAR.

Calling Sequence

int far pascal FSH_SEMWAIT (pSem, cmsTimeout)

void far \ pSem; unsigned long cmsTimeout;

Where

pSem

is the handle to the system semaphore or the long address of the ram semaphore.

cmsTimeout

is the number of milliseconds to wait.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_SEM_TIMEOUT

the timeout expired without gaining access to the semaphore.

ERROR_INTERRUPT

the current thread received a signal.

ERROR_PROTECTION_VIOLATION

the semaphore is inaccessible.

Remarks

The caller may return after the timeout period has expired without receiving an ERROR_SEM_TIMEOUT. Semaphore timeout values, therefore, should not be used for exact timing and sequence.

FSH_SEMWAIT may block.

FSH_SETVOLUME Force a volume to be mounted on the drive

Purpose

This function provides the mechanism for assuring that a desired volume is in a removable media drive before I/O is done to the drive.

Calling Sequence

int far pascal FSH_SETVOLUME (hVPB, fControl)

unsigned short unsigned short hVPB; fControl;

Where

hVPB

is the volume handle for the source of I/O.

fControl

is the bit mask of pop-up control actions:

Bit 0 off indicates volume change pop-up desired

Bit 0 on indicates no volume change pop-up

All other bits are reserved and must be zero.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_VOLUME_CHANGED

is an indication that removable media volume change has occured.

ERROR_INVALID_PARAMETER

the fControl flag word has reserved bits on.

Remarks

This routine is used by the FSH_CALLDRIVER routine to insure that the desired volume is in a removable media drive. FSDs can use it for the same purpose.

FSH_SETVOLUME may block.

FSH_STACKSPACE Determin stack space

Purpose

Query if the current thread is a server thread.

Calling Sequence

int far pascal FSH_STACESPACE (pstackspace)

unsigned long far

pstackspace;

Where

pstackspace

is a pointer to the available stack space.

Returns

Return available stack space. There are no error returns.

FSH_STORECHAR Store a character in a string

Purpose

This function provides the mechanism for storing a character into a string, taking into account DBCS considerations.

Calling Sequence

int far pascal FSH_STORECHAR (chDBCS, ppStr)

 $\begin{array}{ll} unsigned \ short & chDBCS; \\ char \ far \ far \ ppStr; \end{array}$

Where

chDBCS

is the character to be stored. This may be either a single-byte character or a double-byte character with the first byte occupying the low-order position.

ppStr

is the pointer to the character pointer where the character will be stored. This pointer is updated upon return.

Returns

There are no error returns.

Remarks

The FSD is responsible for verifying the string pointer and checking for segment boundaries.

FSH_UPPERCASE Uppercase asciiz string

Purpose

This function is used to uppercase an asciiz string.

Calling Sequence

int far pascal FSH_UPPERCASE (szPathName, cbPathBuf, pPathBuf)

char far \ szPathName; unsigned short cbPathBuf; char far \ pPathBuf;

Where

szPathName

is a pointer to the asciiz pathname to be uppercased.

cbPathBuf

is the length of the pathname buffer.

pPathBuf

is a pointer to the buffer to copy the uppercased path into

Returns

If no error is detected, a zero error code is returned. If an error is detected, the following error code is returned:

ERROR_BUFFER_OVERFLOW

uppercased pathname is too long to fit into buffer.

Remarks

This routine processes DBCS characters properly.

The FSD is responsible for verifying the string pointers and checking for segment boundaries.

szPathName and pPathBuf may point to the same place in memory.

FSH_UPPERCASE should be called for names passed into the FSD in raw data packets which are not passed to FSH_CANONICALIZE and should be uppercased, that is, extended attribute names.

FSH_WILDMATCH Match using OS/2 wildcards

Purpose

This function provides the mechanism for using OS/2 wildcard semantics to form a match between an input string and a pattern, taking into account DBCS considerations.

Calling Sequence

int far pascal FSH_WILDMATCH (pPat, pStr)

 $\begin{array}{ll} char \ far \setminus & pPat; \\ char \ far \setminus & pStr; \end{array}$

Where

pPat

is the pointer to an ASCIIZ pattern string. Wildcards are present and are interpreted as described below.

ppStr

is the pointer to the test string.

Returns

If no error is detected, a zero error code is returned. If an error is detected, the following error code is returned:

ERROR_NO_META_MATCH

the wildcard match failed.

Remarks

Wildcards provide a general mechanism for pattern matching file names. There are two distinguished characters that are relevant to this matching. The '?' character matches one character (not bytes) except at a '.' or at the end of a string, where it matches zero characters. The '*' matches zero or more characters (not bytes) with no implied boundaries except the end-of-string.

For example, "a*b" matches "ab" and "aCCCCCCCb" while "a?b" matches "aCb" but does not match "aCCCCCCCb"

See the section on meta characters in this document for additional information.

The FSD should uppercase the pattern and string before calling FSH_WILDMATCH to achieve a case-insensitive compare.

FSH_YIELD Yield processor to higher-priority thread

Purpose

This function provides the mechanism for relinquishing the processor to higherpriority threads.

Calling Sequence

void far pascal FSH_YIELD (void)

Returns

There are no error returns.

Remarks

FSDs run under the 2ms dispatch latency imposed on the OS/2 kernel, meaning that no more than 2ms can be spent in an FSD without an explicit block or yield. FSH_YIELD will test to see if another thread is runable at the current thread's priority or at a higher priority. If one exists, that thread will be given a chance to run.

Chapter 4. Remote IPL / Bootable IFS

This chapter describes the OS/2 Version 3.0 boot architecture and extensions to the installable file system mechanism(IFSM) to enable booting from an FSD-managed volume, referred to as Bootable IFS(BIFS). If the volume is on a remote system, it is referred to as Remote IPL(RIPL).

The mini-FSD is similar to the FSD defined in this document. However, it has additional requirements for to allow reading of the boot drive before the base device drivers are loaded. These requirements are fully defined in the two interface sections of this chapter.

To satisfy its I/O requests, the mini-FSD may call the disk device device driver imbedded in OS2KRNL(BIFS case) or it may provide its own driver(RIPL case).

Along with the mini-FSD, the IFS SYS Utility is required to initialize an FSD-managed volume with whatever is required to satisfy the requirements of the mini-FSD and this document.

The IFS mechanism includes some additional calls which the mini-FSD may need while it is linked into the IFS chain.

Operational Description

FAT Boot Procedure

The following figure represents the major stages of the OS/2 Version 3.0 FAT boot procedure.

Figure 4-1. OS/2 Version 3.0 FAT boot procedure

Powering-on the machine or pressing CTRL-ALT-DEL causes control to get transferred to the power-on-self-test (POST) code. This code initializes the interrupt vectors to get to the BIOS routines. It then scans the I/O adapters looking for and linking in any code which exists on them. It then executes an interrupt 19h (INT 19) which causes control to be transferred to the disk or diskette boot code.

The INT 19h code reads the boot sector from disk or diskette into memory at 7C00H. Along with code, the boot sector contains a structure called the BIOS Parameter Block(BPB). The BPB contains information which describes how the disk is formatted. The boot code uses this information to load in the root directory and the FAT micro-IFS, which is kept inside the OS2BOOT file. After the micro-IFS is loaded the boot sector transfer control it via a far jump.

OS2BOOT receives pointers to the RAM copies of the root directory and the BPB. Using the BPB information, OS2BOOT loads in the FAT table from the disk. Then using the root directory and the FAT table, the OS2LDR file is loaded into memory from disk. The inclusion of this micro-IFS in the FAT boot process has removed the requirement that the OS2LDR file be logically contigous on the FAT drive.

OS2LDR contains the OS/2 loader. It relocates itself to the top of low memory, then scans the root directory for OS2KRNL and reads it into memory. After the required fixups are applied, control is transferred to OS2KRNL, along with a pointer to the BPB and the drive number.

OS2KRNL contains the OS/2 kernel and initialization code. It switches to protected mode, relocates parts of itself to high memory, then scans the root directory for and reads in the base device drivers (stage 1). Once again, the BIOS interrupt 13h is used to read the disk, but mode switching must be done.

OS2KRNL then switches to protection level 3 and loads some of the required dynamic link libraries (stage 2) followed by the device drivers and FSDs specified in CONFIG.SYS (stage 3). This is done with standard DOS calls and, therefore, goes through the regular file system and device drivers.

BIFS Boot Procedure

The following figure represents the major stages of the OS/2 Version 3.0 BIFS boot procedure.

Figure 4-2. OS/2 Version 3.0 BIFS boot procedure

The major difference between this boot procedure and the FAT boot procedure is that there is no assumption of booting off of disk. OS/2 Version 3.0 does not define what should happen between when the POST code is run and when the OS2LDR program gains control.

When OS2LDR receives control, it must be passed information about the current state of memory and pointers to the Open, Read, Close, and Terminate entry points of the micro-FSD. Included in the memory map information is the positions of the micro-FSD, mini-FSD, RIPL data, and the OS2LDR file itself.

Note: This interface is defined in a next section of this chapter.

As with the FAT boot procedure, the OS/2 loader relocates itself to the top of low memory, and with the help of the micro-FSD, scans the root directory for the OS2KRNL file. After reading OS2KRNL into memory and applying the required fixups, control is transferred to the kernel.

When OS2KRNL receives control, it goes through the same initialization as before (stage 1) with a couple of exceptions. The module loader is called to load the mini-FSD from its memory image stored by OS2LDR in high memory to its final location at the top of low memory. Also, the mini-FSD is called to read the base device drivers (one at a time) through the stage 1 interfaces.

Before any of the dynalinks are loaded, the mini-FSD will be linked into the IFS chain (it will be the only link in the chain) and asked to initialize through FS_INIT. The FS_INIT call marks the transition from stage 1 to stage 2.

The dynalinks are then loaded using the stage 2 interfaces, followed by the device drivers and FSDs.

The mini-FSD is required to support only a small number of the FSD system interfaces (the FS_xxxx calls). Therefore, the first FSD loaded must be the replacement for the mini-FSD.

After the replacement FSD has been loaded, it is called at FS_INIT to initialize itself and take whatever action it needs to effect a smooth transition from the mini-FSD to the FSD. It then replaces the mini-FSD in the IFS chain, as well as in any kernel data structures which keep a handle to the FSD (for example, the SFT, VPB). This replacement marks the transition from stage 2 to stage 3.

From this point on, the system continues normally.

BlackBox/OS2LDR interface

When initially transferring control to OS2LDR from a "black box", the following interface is defined:

DH

boot mode flags:

bit 0 (NOVOLIO) on indicates that the mini-FSD does not use mFSH_DOVOLIO.

bit 1 (RIPL) on indicates that boot volume is not local (RIPL boot)

bit 2 (MINIFSD) on indicates that a mini-FSD is present.

bit 3 (RESERVED)

bit 4 (MICROFSD) on indicates that a micro-FSD is present.

bits 5-7 are reserved and MUST be zero.

DL

drive number for the boot disk. This parameter is ignored if either the NOVOLIO or MINIFSD bits are zero.

DS:SI

is a pointer to the BOOT Media's BPB. This parameter is ignored if either the NOVOLIO or MINIFSD bits are zero.

ES:DI

is a pointer to a filetable structure. The filetable structure has the following format:

struct FileTable {

| shader i ne ruble (|
|---|
| unsigned short ft_cfiles; $\land \#$ of entries in this table \land |
| unsigned short ft_ldrseg; \land paragraph # where OS2LDR is loaded \land |
| unsigned long ft_ldrlen; \land length of OS2LDR in bytes \land |
| unsigned short ft_museg; /paragraph # where microFSD is loaded X |
| unsigned long ft_mulen; Alength of microFSD in bytes |
| unsigned short ft_mfsseg; /paragraph # where miniFSD is loaded X |
| unsigned long ft_mfslen; \land length of miniFSD in bytes \land |
| unsigned short ft_ripseg; \wedge paragraph # where RIPL data is loaded \vee |
| unsigned long ft_riplen; \land length of RIPL data in bytes \land |
| \land The next four elements are pointers to microFSD entry points \land |
| unsigned short (far ft_muOpen) |
| (char far pName, unsigned long far pulFileSize); |
| unsigned long (far ft_muRead) |
| (long loffseek, char far pBuf, unsigned long cbBuf); |
| unsigned long (far ft_muClose)(void); |
| unsigned long (far ft_muTerminate)(void); |
| } |
| |

The microFSD entry points interface is defined as follows:

mu_Open - is passed a far pointer to name of file to be opened and a far pointer to a ULONG to return the file's size. The returned value(in AX) indicates $success(\theta)$ or failure(non- θ).

mu_Read - is passed a seek offset, a far pointer to a data buffer, and the size of the data buffer. The returned value(in DX:AX) indicates the number of bytes actually read.

- mu_Close has no parameters and expects no return value. It is a signal to the micro-FSD that the loader is done reading the current file.
- mu_Terminate has no parameters and expects no return value. It is a signal to the micro-FSD that the loader has finished reading the boot drive.

The loader will call the micro-FSD in a Open-Read-Read-....-Read-Close sequence with each file read in from the boot drive.

miniFSD/OS2KRNL interface

When called from OS2KRNL after being linked into the IFS chain, the interface will be as described in previous chapters of this document. Note that the FS_INIT interface for a mini-FSD has an additional parameter, as compared to the FS_INIT interface for an FSD.

When called from OS2KRNL, before being linked into the IFS chain, the interface will be through the MFS_xxxx and MFSH_xxxx entry points. These interfaces are described in this chapter. Many of these interfaces parallel the interfaces defined for FSDs, while others are unique to the mini-FSD.

The mini-FSD is built as a dynamic link library. Supplied functions are exported by making the function names public. Helper functions are imported by declaring the helper names external:far. It is required only to support reading files and will be called only in protect mode. The mini-FSD may NOT make dynamic link system calls at initialization time.

Due to the special state of the system as it boots, the programming model for the mini-FSD during the state 1 time frame is somewhat different than the model for stage 2. This difference necessitates 2 different interfaces between OS/2 and the mini-FSD.

During stage 1, all calls to the mini-FSD are to the MFS_xxxx functions. Only the MFSH_xxxx helper functions are available. These are the interfaces which are addressed in this document. Many of these interfaces parallel the interfaces defined for FSDs while others are unique to the mini-FSD.

During stage 2, the mini-FSD is treated as a normal FSD. Calls are made to the FS_xxxx functions and all FSH_xxxx helper functions are available.

During stage 3, the mini-FSD is given a chance to release resources (through a call to MFS_TERM) before being terminated.

Transition from stage 1 to stage 2 is marked by calling the FS_INIT function in the mini-FSD. Transition from stage 2 to stage 3 is marked by calling FS_INIT in the FSD.

Figure 4-3 on page 4-6 shows the functions called during a typical boot sequence:

MFS_INIT MFS_OPEN MFS_READ MFS_CHGFILEPTR MFS_CLOSE

> FS_INIT FS_MOUNT/ATTACH FS_OPEN FS_READ FS_CHGFILEPTR

MFS_TERM

Figure 4-3. Typical boot sequence

No files are open at the transition from stage 1 to stage 2. Also, only a single file at a time is open during stage 1. Files and volumes are open during the transition from stage 2 to stage 3 (the mini-FSD to the FSD). The FSD must do whatever is necessary for it to inherit them. The FSD will not receive mounts/attaches or opens for volumes and files which were mounted/attached and opened by the mini-FSD. Also, multiple files may be open simultaneously during stages 2 and 3.

A special set of helper functions are available to the mini-FSD to support an imbedded device driver. This might be required for situations such as remote IPL where the boot volume is not readable through DOVOLIO. These special helper functions (referred to as imbedded device driver helpers) are available during all stages of the mini-FSD's life. Note that the list of error return codes for the helper functions is not exhaustive, but rather represents the most common errors returned.

Because the mini-FSD is a new component added to the boot sequence, a new interface to OS2LDR is required.

The name and attributes of the mini-FSD must match EXACTLY the name and attributes of the replacement FSD.

Due to the instability of the system during initialization, any non-zero return code indicates an error has been encountered. The actual return code may not bake any sense in the context of the function called (for example, having ERROR_ACCESS_DENIED returned from a call to MFSH_LOCK when in fact an invalid selector was passed to the helper). It is also possible for the system to hang or reboot itself as a result of invalid parameters being passed to a helper function.

Stage 1 Interfaces

The following functions must be made available by the mini-FSD. These functions will be called only during stage 1.

MFS_CHGFILEPTR MFS_CLOSE MFS_INIT MFS_OPEN MFS_READ MFS_TERM

The following helper functions are available to the mini-FSD. These functions may be called only during stage 1.

MFSH_DOVOLIO MFSH_INTERR MFSH_SEGALLOC MFSH_SEGFREE MFSH_SEGREALLOC

Stage 2 Interfaces

The intent of stage 2 is to use the mini-FSD as an FSD. Therefore, all the guidelines and interfaces specified in this document apply with the following exceptions.

The following functions must be fully supported by the mini-FSD:

FS_ATTACH (remote mini-FSD only) FS_ATTRIBUTE FS_CHGFILEPTR FS_CLOSE FS_COMMIT FS_INIT FS_IOCTL FS_MOUNT (local mini-FSD only) FS_NAME FS_OPENCREATE (existing file only) FS_PROCESSNAME FS_READ

Note that since the mini-FSD is only required to support reading, FS_OPENCREATE need only support opening an existing file (not the create or replace options).

None of the other functions required for FSDs are required for the mini-FSD but must be defined and should return the ERROR_UNSUPPORTED_FUNCTION return code.

The full complement of helper functions specified in this document is available to the mini-FSD. However, the mini-FSD may NOT use any other dynamic link calls.

Stage 3 Interfaces

The intent of stage 3 is to throw away the mini-FSD and use only the FSD.

The following functions must be supported by the mini-FSD:

MFS_TERM

Imbedded Device Driver Helpers

The following helper functions are available to the mini-FSD and may be called during stage 1, 2, or 3. These helpers are counterparts for some of the device help functions and are intended for use by a device driver imbedded within the mini-FSD.

MFSH_CALLRM MFSH_LOCK MFSH_PHYSTOVIRT MFSH_UNLOCK MFSH_UNPHYSTOVIRT MFSH_VIRTTOPHYS

Special Considerations

The size of the mini-FSD file image plus the RIPL data area may not exceed 62K. In addition, the memory requirements of the mini-FSD may not exceed 64K.

The mini-FSD is only required to support reading of a file. Therefore, any call to DosWrite (or other non-supported functions) which becomes redirected to the mini-FSD may be rejected. For this reason, it is required that the IFS= command which loads the FSD which will replace the mini-FSD be the first IFS= command in CONFIG.SYS. Also, only DEVICE= commands which load device drivers required by that FSD should appear before the first IFS= command.

If the mini-FSD needs to switch to real mode, it must use the MFSH_CALLRM function. This is required to keep OS/2 informed of the mode switching.

Each FSD which is bootable is required to provide their "black box" to load OS2LDR and the mini-FSD into memory before OS2LDR is given control.

Additionally, these FSDs are required to provide a single executable module in order to support the OS/2 SYS utility. The executable provided will be invoked by this utility when performing a SYS for that file system. The command line that was passed to the utility will be passed unchanged to the executable.

The supplied executable must do whatever is required to make the partition bootable. At the very least, it must install a boot sector. It also needs to install the "black box", mini-FSD, OS2LDR and OS2KRNL.

mini-FSD Entry Points

The following table is a summary of mini-FSD entry points:

Table 4-1. Summary of mini-FSD entry points

| Entry Point | Description. |
|----------------|--------------------------------|
| MFS_CHGFILEPTR | Move a file's position pointer |
| MFS_CLOSE | Close a file. |
| MFS_INIT | mini-FSD initialization |
| MFS_OPEN | Open a file |
| MFS_READ | Read from a file |
| MFS_TERM | Terminate the mini-FSD |

MFS_CHGFILEPTR Move a file's position pointer

Purpose

Move the file's logical read position pointer.

offset;

type;

Calling Sequence

int far pascal MFS_CHGFILEPTR (offset, type)

long unsigned short

Where

offset

is the signed offset which depending on the type parameter is used to determine the new position within the file.

type

indicates the basis of a seek operation.

- type == 0 indicates seek relative to beginning of file. type == 1 indicates seek relative to current position within the file.
- type == 2 indicates seek relative to end of file.

Remarks

The file system may want to take the seek operation as a hint that an I/O operation is about to take place at the new position and initiate a positioning operation on sequential access media or read-ahead operation on other media.

Returns

If no error is detected, a zero error code is returned. If an error is detected, a non-zero erro code is returned.

Remarks

None

MFS_CLOSE Close a file

Purpose

Close a file.

Calling Sequence

int far pascal MFS_CLOSE (void)

Returns

If no error is detected, a zero error code is returned. If an error is detected, a non-zero erro code is returned.

Remarks

None

MFS_INIT mini-FSD Initialization

Purpose

Inform the mini-FSD that it should prepare itself for use.

Calling Sequence

int far pascal MFS_INIT (pBootData , pucResDrives , pulVectorIPL, pBPB , pMiniFSD , pDumpAddr)

void far \ pBootData; char far \ pucResDrives; long far \ pulVectorIPL; void far \ pBPB; unsigned long far \ pMiniFSD; unsigned long far \pDumpAddr;

Where

pBootData

is a pointer to the data passed from the black box to the mini-FSD(null if not passed).

pucResDrives

is a pointer to a byte which may be filled in by the mini-FSD with the number of drive letters (beginning with 'C') to skip over before assigning drive letters to local fixed disk drivers (ignored if not remote IPL). The system will attach the reserved drives to the mini-FSD through a call to FS_ATTACH just after the call to FS_INIT.

pulVectorIPL

is a pointer to a double word which may be filled in by the mini-FSD with a pointer to a data structure which will be available to installable device drivers through the standard device helper function GetDosVar(variable number 12). The first eight bytes of the structure MUST be a signature which would allow unique identification of the data by cooperating device drivers (for example, IBMPCNET).

BPB

is a pointer to the BPB data structure (see OS2LDR interface).

pMiniFSD

is a pointer to a double word which is filled in by the mini-FSD with data to be passed on to the FSD.

DumpRoutine

is a pointer to a double word which is filled in by the mini-FSD with the address of an alternative stand-alone dump procedure.

Returns

If no error is detected, a zero error code is returned. If an error is detected, a non-zero erro code is returned.

Remarks

The mini-FSD should fill in the data pointed to by pMiniFSD with any 32-bit value it wishes to pass on to the FSD (see FS_INIT). OS/2 makes no assumptions about the type of data passed. Typically, this will be a pointer to important data structures within the mini-FSD which the FSD needs to know about.

OS/2 will not free the segment containing BootData. It should be freed by the mini-FSD if appropriate.

The DumpProcedure is a routine provided by the mini-FSD which replaces the diskette-based OS/2 stand-alone dump procedure. This routine is given control after the OS/2 kernel receives a stand-alone dump request. The OS/2 kernel places the machine in a stable, real mode state in which most interrupt vectors contain their original power-up value. If this address is left at zero, the OS/2 kernel will attempt to initiate a storage dump to diskette, if a diskette drive exists. The provided routine must handle the dumping of storage to an acceptable media.

MFS_OPEN Open a file

Purpose

Open the specified file.

Calling Sequence

int far pascal MFS_OPEN (pszName , pulSize)

char far \ pszName; unsigned long far \ pulSize;

Where

pszName

is a pointer to the ASCIIZ name of the file to be opened. It may include a path but will not include a drive.

pulSize

is a pointer to a double word which is filled in by the mini-FSD with the size of the file in bytes.

Returns

If no error is detected, a zero error code is returned. If an error is detected, a non-zero erro code is returned.

Remarks

Only one file at a time will be opened by this call. The drive will always be the boot drive.

The current file position is set to the beginning of the file.

MFS_READ Read from a file

Purpose

Read the specified number of bytes from the file to a buffer location.

Calling Sequence

int far pascal MFS_READ (pcData , pusLength)

char far \ pcData; unsigned long far \ pusLength;

Where

pcData

is a pointer to the data area to be read into. The data area is guaranteed to be below the 1-Meg boundary.

pusLength

is a pointer to a word which on entry specifies the number of bytes to be read. On return, it is filled in by the mini-FSD with the number of bytes successfully read.

Returns

If no error is detected, a zero error code is returned. If an error is detected, a non-zero erro code is returned.

Remarks

The current file position is advanced by the number of bytes read.

MFS_TERM Terminate the mini-FSD

Purpose

Inform the mini-FSD that it should prepare itself for termination.

Calling Sequence

int far pascal MFS_TERM (void)

Returns

If no error is detected, a zero error code is returned. If an error is detected, a non-zero erro code is returned.

Remarks

The system will NOT free any memory explicitly allocated by the mini-FSD through MFSH_SEGALLOC or FSH_SEGALLOC. It must be explicitly freed by the mini-FSD. (Memory allocated by the mini-FSD and 'given' to the FSD need not be freed.) The system will free all of the segments loaded as part of the mini-FSD image immediately after this call.

mini-FSD Helper Routines

The following table summaries the mini-FSD Helper Routines:

| Table 4 | 4-2. | Summary | of mini-FS | D Helpers |
|---------|------|---------|------------|-----------|
|---------|------|---------|------------|-----------|

| FSD Helper | Description |
|-------------------|--|
| MFSH_CALLRM | Put machine in real mode |
| MFSH_DOVOLIO | Read sectors |
| MFSH_INTERR | Internal error |
| MFSH_LOCK | Lock segment |
| MFSH_PHYSTOVIRT | Convert physical to virtual address |
| MFSH_SEGALLOC | Allocate a segment |
| MFSH_SEGFREE | Free a segment |
| MFSH_SEGREALLOC | Change segment size |
| MFSH_SETBOOTDRIVE | Change boot drive number kept by the OS/2 kernel |
| MFSH_UNLOCK | Unlock a segment |
| MFSH_UNPHYSTOVIRT | Mark completion of use of virtual address |
| MFSH_VIRT2PHYS | Convert virtual to physical address |

MFSH_CALLRM Put machine in real mode

Purpose

Put the machine into real mode, call the specified routine, put the machine back into protect mode, and return.

Calling Sequence

int far pascal MFSH_CALLRM (plRoutine)

unsigned long far \ plRoutine;

Where

plRoutine

is a pointer to a double word which contains the VIRTUAL address of the routine to call.

Returns

There are no error returns.

Remarks

Only registers DS and SI will be preserved between the caller and the target routine. The selector in DS will be converted to a segment before calling the target routine. Arguments may not be passed on the stack since a stack switch may occur.

This helper allows the mini-FSD to access the ROM BIOS functions which typically run in real mode only. Great care must be taken in using this function since selectors used throughout the system are meaningless in real mode. While in real mode, no calls to any helpers may be made.

MFSH_DOVOLIO Read sectors

Purpose

Read the specified sectors.

Calling Sequence

int far pascal MFSH_DOVOLIO (pcData, pcSec, ulSec)

char far \ pcData; unsigned short far \ pcSec; unsigned long ulSec;

Where

pcData

is a pointer to the data area. The data area must be below the 1-Meg boundary.

pcSec

is a pointer to the word which specifies the number of sectors to be read. On return, it is filled in by the helper with the number of sectors successfully read.

ulSec

is the sector number for the beginning of the sector run.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_PROTECTION_VIOLATION

the supplied address or length is invalid.

ERROR_INVALID_FUNCTION

either bit 0 of the boot mode flags was set on entry to OS2LDR or the system is not in stage 1.

Remarks

The only media which can be read by this call is the boot volume. The machine's interrupt 13H BIOS function is used to actually do the disk reads. The data area will be locked and unlocked by this helper. Soft errors are retried automatically. Hard errors are reported to the user through a message and the system is stopped.

MFSH_INTERR Internal Error

Purpose

Declare an internal error and halt the system.

Calling Sequence

int far pascal MFSH_INTERR (pcMsg , cbMsg)

pcMsg;

cbMsg;

char far \ unsigned short

Where

pcMsg is a pointer to the message text.

cbMsg

is the length of the message text.

Returns

There are no error returns.

Remarks

This call should be used when an inconsistency is detected within the mini-FSD. This call does not return. An error message will be displayed and the system will be stopped. See the description of FSH_INTERR.

MFSH_LOCK Lock a segment

Purpose

Lock a segment in place in physical memory.

Calling Sequence

int far pascal MFSH_LOCK (usSel , pulHandle)

unsigned short usSel; unsigned long far \pulHandle;

Where

usSel

is the selector of the segment to be locked.

pulHandle

is a pointer to a double word which is filled in by the helper with the lock handle.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_PROTECTION_VIOLATION

the supplied address or selector is invalid.

Remarks

This helper is for use by a mini-FSD with an imbedded device driver. It is the same as the standard device driver LOCK helper with the following assumptions: The lock is defined to be short term and will block until the segment is loaded.

MFSH_PHYSTOVIRT Convert physical to virtual address

Purpose

Translate the physical address of a data buffer into a virtual address.

Calling Sequence

int far pascal MFSH_PHYSTOVIRT (ulAddr , usLen , pusSel)

unsigned long ulAddr; unsigned short usLen; unsigned short far \pusSel;

Where

ulAddr

is the physical address to be translated.

usLen

is the length of the segment for the physical address.

pusSel

is a pointer to the word in which the selector or segment is returned.

Returns

If an error is not detected, a zero error code is returned. If an error is detected, the following error is returned:

ERROR_PROTECTION_VIOLATION

the supplied address is invalid.

Remarks

This helper is for use by a mini-FSD with an imbedded device driver. It is the same as the standard device driver helper PHYSTOVIRT. A segment/offset pair is returned in real mode for addresses below 1 mb. Else a selector/offset pair is returned.

A caller must issue a corresponding UNPHYSTOVIRT before returning to its caller or using any other helpers.

MFSH_SEGALLOC Allocate a segment

Purpose

Allocate memory.

Calling Sequence

int far pascal MFSH_SEGALLOC (usFlag, cbSeg, pusSel)

unsigned short usFlag; unsigned long cbSeg; unsigned short far \pusSel;

Where

usFlag

is set to 1 if the memory must be below the 1-meg boundary or 0 if its location does not matter.

cbSeg

contains the length of the segment.

pusSel

is a pointer to a word in which the helper returns the selector of the segment.

Returns

If no error is detected, a zero error code is returned. If an error is detected, one of the following error codes is returned:

ERROR_NOT_ENOUGH_MEMORY

too much memory is allocated.

ERROR_PROTECTION_VIOLATION

the supplied address is invalid.

ERROR_INVALID_PARAMETER

either the supplied flag or length is invalid.

Remarks

This function allocates memory with the following attributes:

Allocated from the GDT Non-swappable

Memory not allocated specifically below the 1-Meg boundary may be given to the FSD by passing the selectors through pMiniFSD (see MFS_INIT and FS_INIT).

MFSH_SEGFREE Free a segment

Purpose

Free a memory segment.

Calling Sequence

int far pascal MFSH_SEGFREE (usSel)

unsigned short usSel;

Where

usSel

contains the selector of the segment to be freed.

Returns

If no error is detected, a zero error error code is returned. If an error is detected, the following error code is returned:

ERROR_PROTECTION_VIOLATION

the selector is invalid.

Remarks

This function releases a segment previously allocated with MFSH_SEGALLOC, or loaded as part of the mini-FSD image.

MFSH_SEGREALLOC Change segment size

Purpose

Change the size of memory.

Calling Sequence

int far pascal MFSH_SEGREALLOC (usSel, cbSeg)

usSel;

cbSeg;

unsigned short unsigned long

Where

usSel

contains the selector of the segment to be resized.

cbSeg

contains the new length of the segment.

Returns

If no error is detected, a zero error code is returned. If an error is detected, on of the following error codes is returned:

ERROR_NOT_ENOUGH_MEMORY

too much memory is allocated.

ERROR_PROTECTION_VIOLATION

the supplied selector is invalid.

ERROR_INVALID_PARAMETER

the supplied length is invalid.

Remarks

This call changes the size of a segment previously allocated with MFSH_SEGALLOC, or loaded as part of the mini-FSD image.

The segment may be grown or shrunk. When grown, the extra space is uninitialized. The segment may be moved in the process.

MFSH_SETBOOTDRIVE Change boot drive number kept by the OS/2 kernel

Purpose

Change boot drive number kept by the kernel to allow a change in the assignment of boot drive as seen by later processes.

Calling Sequence

int far pascal MFSH_SETBOOTDRIVE (usDrive)

unsigned short usDrive;

Where

usDrive

contains the 0-based drive number that the mini-FSD wants the system to consider as the boot drive.

Returns

If no error is detected, a zero error code is returned. If an error is detected, on of the following error codes is returned:

ERROR_INVALID_PARAMETER

the supplied drive number is invalid.

Remarks

This call changes the boot drive number that is kept in the global info segment of the system. Valid values range from 2(=C) to 25(=Z). This function must be called during the call to MFS_INIT to update the info segment correctly. This is routine should be used by RIPL mini-FSDs.

MFSH_UNLOCK Unlock a segment

Purpose

Unlock a segment which was previous locked by calling MFSH_LOCK.

Calling Sequence

int far pascal MFSH_SEGREALLOC (ulHandle)

unsigned long ulHandle;

Where

ulHandle

contains the handle returned from MFSH_LOCK of the segment to unlock.

Returns

If no error is detected, a zero error code is returned. If an error is detected, the following error code is returned:

ERROR_PROTECTION_VIOLATION

the supplied address is invalid.

Remarks

This helper is for use by a mini-FSD with an imbedded device driver. It is the same as the standard device driver helper UNLOCK.

MFSH_UNPHYSTOVIRT Mark completion of use of virtual address

Purpose

Release the selector allocated previously by calling MFSH_PHYSTOVIRT.

Calling Sequence

int far pascal MFSH_UNPHYSTOVIRT (usSel)

unsigned short usSel;

Where

usSel

contains the selector to released.

Returns

If no error is detected, a zero error code is returned. If an error is detected, the following error code is returned:

ERROR_PROTECTION_VIOLATION

the supplied selector is invalid.

Remarks

This helper is for use by a mini-FSD with an imbedded device driver. It is the same as the standard device driver UNPHYSTOVIRT helper.

A caller must issue a corresponding UNPHYSTOVIRT after calling PHYSTOVIRT, before returning to its caller or using any other helpers.

MFSH_VIRT2PHYS Convert virtual to physical address

Purpose

Translate the address of a data buffer into a physical address.

Calling Sequence

int far pascal MFSH_VIRT2PHYS (ulVirtAddr, pulPhysAddr)

unsigned long ulVirtAddr; unsigned long far \pulPhysAddr;

Where

ulVirtAddr

contains the virtual address of the data area.

PhysAddr

is a pointer to a double word in which the helper returns the physical address of the data area.

Returns

If no error is detected, a zero error code is returned. If an error is detected, the following error is returned:

ERROR_PROTECTION_VIOLATION

the supplied address is invalid.

Remarks

This helper is for use by a mini-FSD with an imbedded device driver. It is the same as the standard device driver helper VIRTTOPHYS.

Chapter 5. Index

Α

access to EAs, controlling 1-11 allocate segment 3-41 API, extended file I/O 1-4 API, standard file I/O 1-2 attach to an FSD 2-4 attributes, FSDs. 1-12

В

BIFS 4-1 BIFS boot procedure 4-3 boot partition 1-6 boot procedure 4-3 boot sector 4-2 bootable IFS 4-1 BPB 4-2 buffer management 1-5

С

caching 1-5 calling conventions, FSDs 1-22 cancel file lock request 2-6 canonicalization 2-72, 3-7 cdfsd, current directory parameters 1-20 cdfsi, current directory parameters 1-20 CDS 1-19 change/verify directory path 2-7 character pointer 3-32 character validation 1-10 CHKDSK 1-7 clear semaphore 3-45 close a file 2-12 commit a file's buffers to disk 2-13 commit file buffers 2-46 CONFIG.SYS statements 1-6 CONFIG.SYS, IFS= 1-13 copy a file 2-15 CPU time 1-22 current directory parameters, cdfsd 1-20 current directory parameters, cdfsi 1-20 current directory prefix 3-29 current directory structure 1-19 current directory, data structures 1-20

current I/O priority, boost 3-27 current I/O priority, determine 3-24

D

Data Structures, FSD current directory 1-20 disk media and file system layout 1-19 file search records 1-21 open files 1-20 time stamps 1-22 data structures, FSDs 1-19 data, file-system-dependent 1-19 data, file-system-independent 1-19 date, format of 1-17 delete a file 2-17 device I/O control 2-52 directory search, begin 2-33 directory search, continue 2-39 directory search, end 2-32 disk media and file system layout 1-19 disk partitions 1-6 DOS partition 1-6 DosDevIOCtl 2-52 DosFsCtl 1-4 DosOpen 2-65 DosQFsAttach 1-7 DosQFSInfo 2-50 DosQPathInfo 2-71 DosQSysInfo 2-72 DosSetFSInfo 2-50 DosSetPathInfo 2-71 DPB 1-5 drive parameter block 1-5 drives and file systems 1-5

Ε

EA manipulation 1-11 EA name validity 3-9 EAOP 1-11 end of process 2-20 entry points, FSDs (summary) 2-1 error return codes, file I/O 1-17 extend thread's time slice 3-19 Extended Attributes EA name validity 3-9 FAT file system 1-11 Extended Attributes (continued) FEAs 1-9 GEAs 1-10 extended boot structure 1-14 extended file API 2-47 extended file I/O API 1-4 Extended strategy call 3-5

F

family API 1-7 FAT file system 1-5 FAT partition 1-6 FEAlist 1-10 FEAs 1-9 features, IFS 1-1 file access, lock 2-29 file access, unlock 2-29 file handles 1-16 File I/O API extend file I/O API 1-4 standard file I/O API 1-2 File I/O bit, FIO 1-13 file image 1-12 file image, mini-FSD 4-9 file information 2-70 file instance, open files 1-21 file lock request, cancel 2-6 file search parameters, fsfsd 1-21 file search parameters, fsfsi 1-21 file search records, data structures 1-21 file search structures 1-19 file size, change 2-60 file system control 2-47 file system driver, FSD 1-2 file system information 2-50 file system initialization 2-51 file version levels 1-16 file-system-dependent data 1-19 file-system-independent data 1-19 FILEIO, File I/O bit 1-13 find character in string 3-20 find matching file name 2-33, 2-37, 2-39 find-notify handle, close 2-41 find-notify handle, open 2-42 flush cache buffers 2-46 FORMAT 1-7 free segment 3-43 **FS** Helper Functions FSH_ADDSHARE 3-3 FSH CALLDRIVER 3-5

FS Helper Functions (continued) FSH CANONICALIZE 3-7 FSH CHECKEANAME 3-9 FSH_CRITERROR 3-10 FSH_DEVIOCTL 3-12 FSH_DOVOLIO 3-14 FSH DOVOLIO2 3-17 FSH_EXTENDTIMESLICE 3-19 FSH_FINDCHAR 3-20 FSH_FINDDUPHVPB 3-21 FSH FORCENOSWAP 3-22 FSH_GETPRIORITY 3-24 FSH_GETVOLPARM 3-25 FSH_INTERR 3-26 FSH_IOBOOST 3-27 FSH_IOSEMCLEAR 3-28 FSH_ISCURDIRPREFIX 3-29 FSH_LOADCHAR 3-30 FSH_NAMEFROMSFN 3-31 FSH_PREVCHAR 3-32 FSH_PROBEBUF 3-33 FSH_QSYSINFO 3-35 FSH QUERYOPLOCK 3-37 FSH_QUERYSERVERTHREAD 3-38 FSH_REGISTERPERFCTRS 3-39 FSH_REMOVESHARE 3-40 FSH_SEGALLOC 3-41 FSH_SEGFREE 3-43 FSH_SEGREALLOC 3-44 FSH_SEMCLEAR 3-45 FSH SEMREQUEST 3-46 FSH_SEMSET 3-48 FSH_SEMSETWAIT 3-49 FSH_SEMWAIT 3-50 FSH SETVOLUME 3-51 FSH_STACKSPACE 3-52 FSH_STORECHAR 3-53 FSH_UPPERCASE 3-54 FSH WILDMATCH 3-55 FSH_YIELD 3-56 summary 3-1 FS helpers 1-2 FSA LOCK 1-13 FSA REMOTE 1-13 FSD entry points FS_ALLOCATEPAGESPACE 2-3 FS_ATTACH 2-4 FS_CANCELLOCKREQUEST 2-6 FS_CHDIR 2-7 FS_CHGFILEPTR 2-10

FSD entry points *(continued)* FS_CLOSE 2-12 FS COMMIT 2-13 FS_COPY 2-15 FS_DELETE 2-17 FS_DOPAGEIO 2-18 FS EXIT 2-20 FS_FILEATTRIBUTE 2-21 FS_FILEINFO 2-23 FS_FILEIO 2-26 FS FILELOCKS 2-29 FS_FINDCLOSE 2-32 FS_FINDFIRST 2-33 FS_FINDFROMNAME 2-37 FS_FINDNEXT 2-39 FS_FINDNOTIFYCLOSE 2-41 FS_FINDNOTIFYFIRST 2-42 FS_FINDNOTIFYNEXT 2-44 FS_FLUSHBUF 2-46 FS_FSCTL 2-47 FS_FSINFO 2-50 FS_INIT 2-51 FS IOCTL 2-52 FS_MKDIR 2-54 FS_MOUNT 2-56 FS_MOVE 2-58 FS_NEWSIZE 2-60 FS_NMPIPE 2-61 FS_OPENCREATE 2-65 FS_OPENPAGEFILE 2-68 FS PATHINFO 2-70 FS_PROCESSNAME 2-72 FS_READ 2-73 FS_RMDIR 2-75 FS SETSWAP 2-76 FS SHUTDOWN 2-77 FS_VERIFYUNCNAME 2-79 FS_WRITE 2-80 summary 2-1 FSD version number 1-13 FSD, file system driver 1-2 fsfsd, file search parameters 1-21 fsfsi, file search parameters 1-21 FSH_CHECKEANAME 1-10 FSH_UPPERCASE 1-10 function calls, file system 1-16

G

GEAList 1-10 GEAs 1-10

Η

hard error, signal 3-10 helper callouts, FSDs (summary) 3-1 hVPB 3-21

I

I/O event semaphore, clear 3-28 IFS = statement 1-16 IFS Commands IFS= statement 1-16 IFS partition 1-6 IFS=, CONFIG.SYS 1-13 initialization, file system 2-51 initialization, FSD 1-13 INT 19H 4-2 internal errors 3-26 interrupts 1-22 IOCTL request to device driver 3-12 ipl mechanism 1-6 IPL, remote 4-1

Κ

kernel mode 1-22

L

load character 3-30 loading a file system 1-16 loading device drivers and FSDs 1-6 loading FSDs 1-13

Μ

make subdirectory 2-54 matching wildcards 3-55 meta characters micro-IFS, FAT 4-2 mini-FSD 4-1 mini-FSD Entry Points MFS_CHGFILEPTR 4-11 MFS_CLOSE 4-12 MFS_INIT 4-13 MFS_OPEN 4-15 MFS_READ 4-16 MFS_TERM 4-17 summary 4-10 mini-FSD helpers MFSH CALLRM 4-19 MFSH DOVOLIO 4-20 MFSH_INTERR 4-21 MFSH_LOCK 4-22 MFSH_PHYSTOVIRT 4-23 MFSH SEGALLOC 4-24 MFSH_SEGFREE 4-25 MFSH_SEGREALLOC 4-26 MFSH_SETBOOTDRIVE 4-27 MFSH UNLOCK 4-28 MFSH_UNPHYSTOVIRT 4-29 MFSH_VIRT2PHYS 4-30 summary 4-18 monitor file/directory changes, begin 2-42 monitor file/directory changes, continue 2-44 monitor file/directory changes, end 2-41 mount volumes 2-56 mount, force 3-51 mounting a volume 1-5 move a file or subdirectory 2-58 move a file's position pointer 2-10 multi-function file I/O 2-26

Ν

name shared set 3-3, 3-37, 3-38, 3-40, 3-52 named pipe operation, remote 2-61 names, FSDs 1-12

0

open a file 2-65 open file parameters, sffsd 1-21 open file parameters, sffsi 1-21 open files, data structures 1-20 openmode parameter 2-65 OS/2 loader 4-2 OS2BOOT 4-2 OS2KRNL 4-2 OS2KRNL 4-2 OS2KRNL interface 4-5 OS2LDR 4-2 OS2LDR interface 4-4

Ρ

paging file size, change 2-3 paging file, create 2-68 paging file, open 2-68 paging I/O, operations 2-18 path name 3-31 path name, canonical form 3-7 PDB, program data block 1-21 PID, process ID 1-21 POST 4-2 power-on-self-test 4-2 PREFVIEW, registration 3-39 process file name 2-72 process ID, PID 1-21 program data block, PDB 1-21 pseudo-character devices 1-7

Q

query/set a file's information 2-23, 2-70 query/set file attribute 2-21

R

read from a file 2-73 RECOVER 1-7 register usage, FSDs 1-22 remote file system, REMOTE 1-13 remote IPL 4-1 remote named pipe operation 2-61 REMOTE, remote file system 1-13 removable media, volume management 1-5 remove subdirectory 2-75 request router, file system 1-2 request semaphore 3-46 RIPL 4-1

S

segment size 3-44 Semaphore FS helpers FSH_SEMCLEAR 3-45 FSH_SEMREQUEST 3-46 FSH_SEMSET 3-48 FSH SEMSETWAIT 3-49 FSH_SEMWAIT 3-50 set and wait for semaphore 3-49 set semaphore 3-48 sffsd, open file parameters 1-21 sffsi, open file parameters 1-21 SFN 3-31 SFT 1-19 shared set, name 3-3, 3-37, 3-38, 3-52 shutdown file system 2-77 special considerations, bootable IFS 4-9 ST_CREAT, time stamp flags 1-22 ST_PCREAT, time stamp flags 1-22 ST_PREAD, time stamp flags 1-22 ST_PWRITE, time stamp flags 1-22 ST_SREAD, time stamp flags 1-22 ST_SWRITE, time stamp flags 1-22 stack usage, FSDs 1-22 standard file I/O API 1-2 store character 3-53 subdirectory, make 2-54 swap segments into memory 3-22 swap-file ownership 2-76 SYS 1-7 system file table 1-19 system information 3-35 system interfaces, FSD 1-18 system relationships, ifs 1-1

Т

time stamp flags 1-22 time stamping 1-22 time, format of 1-17

U

UNC server, verify 2-79 UNC, Universal Naming Convention bit 1-13 Universal Naming Convention bit, UNC 1-13 uppercase asciiz string 3-54 user address 3-33 Utility Support CHKDSK 1-7 FORMAT 1-7 RECOVER 1-7 SYS 1-7

V

valid user address 3-33 validation of input parameters 3-1 volume 1-19 volume I/O 3-14 volume IOCTL request to device driver 3-17 volume management, removable media 1-5 volume parameter block 1-5, 1-19 volume parameters, vpfsd 1-19 volume parameters, vpfsi 1-19 volume, force mount 3-51 VPB 1-5, 1-19, 3-25 vpfsd, volume parameters 1-19 vpfsi, volume parameters 1-19

W

wait for semaphore 3-50 wildcards 3-55 write to a file 2-80

Y

yield CPU 3-56

+++EDF074W Revision for REFID=OS24 out of sequence - EREV tag ignored. (Page 3-52 File: IFSH ELP)

DSMMOM397I '.EDFERVBR' WAS IMBEDDED AT LINE 2036 OF 'IFSHELP'

DSMMOM397I 'IFSHELP' WAS IMBEDDED AT LINE 123 OF 'OS2IFS20'

DSMBEG323I STARTING PASS 2 OF 2.

+++EDF074W Revision for REFID=OS24 out of sequence - EREV tag ignored. (Page 3-52 File: IFSH ELP)

DSMMOM397I '.EDFERVBR' WAS IMBEDDED AT LINE 2036 OF 'IFSHELP' DSMMOM397I 'IFSHELP' WAS IMBEDDED AT LINE 123 OF 'OS2IFS20'